

# **Analyzer**

FLUX:: Immersive

2023-02-06

# Table of contents

<b>Welcome to FLUX:: Analyzer</b>	<b>3</b>
A User Guide . . . . .	3
<b>FLUX:: Analyzer Versions</b>	<b>4</b>
<b>Credits</b>	<b>5</b>
Project manager and Designer . . . . .	5
Developed by . . . . .	5
DSP Algorithms Specialist . . . . .	5
DSP development . . . . .	5
Graphic design . . . . .	5
Flux:: Framework development . . . . .	5
additional contributions: . . . . .	6
Flux:: Framework graphic engine . . . . .	6
And . . . . .	6
special thanks to . . . . .	6
Dolby . . . . .	6
FLUX:: . . . . .	6
Additional libs . . . . .	6
Additional Python modules . . . . .	8
Open source libraries . . . . .	9
RTTrPM SDK (Blacktraxx) . . . . .	9
ThorVG (replaces crossed-out libraries above) - MIT . . . . .	10
r8brain free - MIT . . . . .	10
oura fft from lmdsp - MIT (or MIT-like) . . . . .	10
LibJpeg - Custom (BSD-like) . . . . .	10
libpng - PNG Reference Library License version 2 . . . . .	10
Freetype 2 - FreeType License . . . . .	11
Zlib - zlib . . . . .	11
bzip2 - Modified zlib . . . . .	11
Boost - BSL-1.0 . . . . .	11
mimalloc - MIT . . . . .	11
ni-media - MIT . . . . .	11
pfft . . . . .	11
pybind11 . . . . .	11

rtaudio . . . . .	11
rtmidi . . . . .	12
concurrentqueue - Simplified BSD . . . . .	12
readerwriterqueue - Simplified BSD . . . . .	12
assimp . . . . .	13
enet - MIT . . . . .	14
fmt . . . . .	14
functions (Erik Rigtorp) - MIT . . . . .	14
inplace_function - BSL-1.0 . . . . .	14
gtest - "BSD 3-Clause "New" " or "Revised" " . . . . .	14
jsoncpp - MIT . . . . .	15
libcurl - MIT like . . . . .	15
magic_enum - MIT . . . . .	16
nanobench - MIT . . . . .	16
nlohmann_json - MIT . . . . .	17
openddl - MIT . . . . .	17
openvr - "BSD 3-Clause "New" " or "Revised" " . . . . .	18
poly2tri - "BSD 3-Clause "New" " or "Revised" " . . . . .	18
pugixml - MIT . . . . .	19
rapidjson - MIT . . . . .	19
shared_recursive_mutex - MIT . . . . .	20
sentry-native - MIT . . . . .	20
sqlite3 - Public Domain . . . . .	21
sqlite_orm - MIT . . . . .	21
stb - MIT . . . . .	22
utfcpp - BSL-1.0 . . . . .	22
unqlite - BSD 2-clause . . . . .	23
argh (Andrey Mikhaylenko) - LGPLv3 . . . . .	23
chardet (Mark Pilgrim, Daniel Blanchard) - LGPL v2.1 . . . . .	23
charset_normalizer - MIT . . . . .	23
docopt (Vladimir Keleshev) - MIT . . . . .	24
dotenv - "BSD 3-Clause"New" " or "Revised" " . . . . .	24
Open source python libraries . . . . .	25
ecdsa (Peter Pearson) - . . . . .	25
environs (Steven Loria) - MIT . . . . .	26
ffmpeg-python - Apache 2 . . . . .	26
ftputil (Stefan Schwarzer) - BSD . . . . .	27
numpy - "BSD 3-Clause"New" " or "Revised" " . . . . .	27
pendulum - MIT . . . . .	28
psutil (Giampaolo Rodola) - "BSD 3-Clause"New" " or "Revised" " . . . . .	29
watchdog - Apache 2 . . . . .	29
tgcrypto - LGPL v3 . . . . .	30
idna - BSD 3 . . . . .	30

marshmallow - MIT . . . . .	31
packaging - BSD . . . . .	31
paramiko (Jeff Forcier) - LGPL 2.1 . . . . .	32
pathtools - MIT . . . . .	32
ptvsd (Microsoft) - MIT . . . . .	32
pyga (Arun K.R.) - BSD . . . . .	33
pylightxl - MIT . . . . .	34
pyparsing - MIT . . . . .	34
pytzdata - MIT . . . . .	35
winshell (Tim Golden) - MIT . . . . .	35
six (Copyright (c) 2010-2020 Benjamin Peterson - MIT . . . . .	36
Request (Kenneth Reitz) - Apache 2 . . . . .	36
sentry_sdk (Copyright (c) 2018 Sentry) - MIT . . . . .	36
urllib3 - MIT . . . . .	37
certifi (Kenneth Reitz) - MPL-2.0 . . . . .	37
anytree (c0fec0de) - Apache 2 . . . . .	37
boltons - BSD . . . . .	38
msgpack (Inada Naoki) - Apache 2 . . . . .	38
dateutil (Gustavo Niemeyer, Paul Ganssle) - Apache 2 . . . . .	39
PyYAML (Kirill Simonov) - MIT . . . . .	39
<b>Introduction</b>	<b>40</b>
<b>I Initial setup</b>	<b>41</b>
<b>1 SampleGrabber</b>	<b>42</b>
1.1 Principle of operation . . . . .	42
1.2 Network configuration . . . . .	42
1.3 Password . . . . .	43
<b>2 Typical configuration</b>	<b>44</b>
2.1 Autonomous mobile configuration . . . . .	44
2.1.1 Capture . . . . .	44
2.1.2 Analysis . . . . .	44
2.2 Digital Audio Workstation . . . . .	45
2.3 Avid Venue Console . . . . .	46
<b>II User interface</b>	<b>48</b>
<b>3 Global presentation</b>	<b>49</b>
3.1 Header section . . . . .	49
3.2 Body section . . . . .	50

3.3	Mouse commands and conventions . . . . .	50
3.4	Keyboard shortcuts . . . . .	51
3.4.1	Main . . . . .	51
<b>4</b>	<b>Header Section</b>	<b>53</b>
4.1	Main toolbar . . . . .	53
4.1.1	Main Setup . . . . .	53
4.1.2	UI Setup . . . . .	55
4.1.3	IO Configuration Setup . . . . .	56
4.1.4	Hold info text . . . . .	56
4.1.5	Full-screen mode . . . . .	57
4.1.6	Close . . . . .	57
4.1.7	Help / about . . . . .	57
4.2	Left toolbar . . . . .	57
4.2.1	Audio source . . . . .	57
4.2.2	Layout mode . . . . .	57
4.3	Smoothing mode . . . . .	58
4.4	Smoothing detail . . . . .	58
4.5	Curve display . . . . .	60
4.6	Max curve . . . . .	60
4.7	Peak type . . . . .	61
4.8	Peak label . . . . .	61
4.9	Peak range . . . . .	62
<b>5</b>	<b>Main setup</b>	<b>63</b>
5.1	Configuration . . . . .	65
5.2	SampleGrabber . . . . .	65
5.3	Graphic engine . . . . .	66
5.4	Time code . . . . .	67
5.4.1	Display frame rate . . . . .	68
5.4.2	Absolute Timecode . . . . .	68
5.5	Main . . . . .	68
5.5.1	RTA block size . . . . .	68
5.5.2	TF/Sweep Block size . . . . .	69
5.5.3	Overlap Mode . . . . .	69
5.5.4	Analysis window . . . . .	70
5.5.5	Normalization . . . . .	70
5.5.6	Scaling . . . . .	71
5.6	Averaging . . . . .	71
5.6.1	Mode . . . . .	71
5.6.2	Length . . . . .	72
5.7	Various . . . . .	72
5.7.1	Auto-pause threshold . . . . .	72

5.7.2	Metric system . . . . .	72
5.7.3	Temperature . . . . .	72
5.7.4	Preferences reset . . . . .	73
<b>6</b>	<b>IO Configuration</b>	<b>74</b>
6.1	Configuration . . . . .	76
<b>7</b>	<b>Hardware IO</b>	<b>77</b>
7.1	Device . . . . .	77
7.1.1	None . . . . .	77
7.1.2	Your soundcard . . . . .	77
7.2	Sampling rate . . . . .	78
7.3	Buffer size . . . . .	79
7.4	Control panel . . . . .	79
<b>8</b>	<b>Channels</b>	<b>80</b>
8.1	Max number of channels . . . . .	80
8.2	Reference configuration . . . . .	81
<b>9</b>	<b>Signal generator</b>	<b>83</b>
9.1	Output . . . . .	83
<b>10</b>	<b>Channel 1 / Channel 2</b>	<b>85</b>
10.1	Phase invert . . . . .	85
10.1.1	Input . . . . .	85
10.1.2	Output . . . . .	85
<b>III</b>	<b>System measurement</b>	<b>86</b>
<b>11</b>	<b>Introduction</b>	<b>87</b>
<b>12</b>	<b>Initial setup</b>	<b>88</b>
<b>13</b>	<b>Practical considerations for capturing measurement signals</b>	<b>89</b>
13.1	Use a measurement microphone . . . . .	89
13.2	Choose a neutral preamplifier and calibrate it accurately . . . . .	89
13.3	Maximize signal-to-noise ratio . . . . .	89
<b>14</b>	<b>Measurement setup</b>	<b>90</b>
<b>15</b>	<b>Test signals</b>	<b>92</b>

<b>IV Spectrum analysis tools</b>	<b>93</b>
<b>16 Spectrum Analyzer</b>	<b>94</b>
16.1 Presentation . . . . .	94
16.2 Settings . . . . .	96
16.2.1 Block size . . . . .	96
16.2.2 Transform type . . . . .	96
16.2.3 Window type . . . . .	97
16.2.4 Ballistics . . . . .	97
16.2.5 Averaging . . . . .	98
16.2.6 Frequency scaling . . . . .	98
16.2.7 Display range . . . . .	99
16.2.8 Summation . . . . .	101
16.2.9 Channels . . . . .	102
16.2.10 Slide (Real Time waterfall) . . . . .	103
16.2.11 Zoom . . . . .	104
<b>17 Spectrogram</b>	<b>105</b>
17.1 Usage . . . . .	105
17.2 Setup . . . . .	106
17.2.1 Direction . . . . .	107
17.2.2 Log Gain . . . . .	107
17.2.3 Threshold . . . . .	107
17.2.4 Color Mode . . . . .	108
<b>18 Nebula (spatial spectrogram)</b>	<b>110</b>
18.1 Principle of operation . . . . .	110
18.2 Scale . . . . .	112
18.2.1 Focus . . . . .	112
18.2.2 AutoScale . . . . .	113
18.2.3 AutoScale release . . . . .	113
18.2.4 Linear blend range . . . . .	113
18.2.5 Log blending . . . . .	113
18.3 Display . . . . .	114
18.3.1 Fading . . . . .	114
18.3.2 Size factor . . . . .	114
18.3.3 Blur kernel size . . . . .	114
18.3.4 Particle scaling . . . . .	115
18.3.5 Color mode . . . . .	115
<b>19 Wave scope</b>	<b>116</b>
19.1 Setup . . . . .	117
19.1.1 Time . . . . .	117

19.1.2	Color Mode . . . . .	118
<b>V</b>	<b>Level metering tools</b>	<b>119</b>
<b>20</b>	<b>RMS metering</b>	<b>120</b>
20.1	About Metering . . . . .	120
20.2	Introduction . . . . .	121
20.3	Preset . . . . .	121
20.3.1	Custom . . . . .	123
20.3.2	Default . . . . .	123
20.3.3	Ref -18dB A/B/C/K . . . . .	123
20.3.4	Ref -20dB A/B/C/K . . . . .	123
20.3.5	VU meter Standard . . . . .	123
20.3.6	K-System / VU . . . . .	123
20.3.7	K-System / Slow . . . . .	123
20.3.8	DIN 45406 . . . . .	124
20.3.9	Nordic N9 . . . . .	124
20.3.10	BBC Normal . . . . .	124
20.3.11	BBC Slow . . . . .	124
20.3.12	EBU Normal . . . . .	124
20.3.13	EBU Slow . . . . .	124
20.4	Settings . . . . .	126
20.4.1	Reference . . . . .	127
20.4.2	SPL . . . . .	127
20.4.3	Range . . . . .	128
20.4.4	Time . . . . .	128
20.4.5	Scale & split . . . . .	129
20.5	Bar-graph texturing . . . . .	129
<b>21</b>	<b>True peak metering</b>	<b>130</b>
21.1	Preset . . . . .	132
21.1.1	Custom . . . . .	132
21.1.2	Default . . . . .	132
21.1.3	EBU R128 . . . . .	132
21.1.4	EBU R128 Max -3dB . . . . .	132
21.1.5	-48.0 -> +3 . . . . .	132
21.1.6	-144.5 -> +3 . . . . .	133
21.2	Settings . . . . .	133
21.2.1	Range . . . . .	133
21.2.2	Scale . . . . .	133
21.2.3	Time . . . . .	133
21.2.4	Scale & split . . . . .	134



21.2.5	Other	134
<b>22</b>	<b>Loudness metering</b>	<b>135</b>
22.1	Loudness ITU-R BS 1770 & EBU R128 PLOUD	135
22.2	Principles	135
22.2.1	Units	135
22.2.2	Loudness and EBU mode	135
22.2.3	Loudness Range (LRA)	136
22.2.4	Scales	136
22.3	Dolby Dialogue Intelligence	136
22.3.1	Introduction	136
22.3.2	General principle	136
22.3.3	Display	137
22.3.4	Delay and compensation	137
22.3.5	Surround	137
22.3.6	Copyright & patent information	138
22.4	Controls and display	139
22.4.1	Display	139
22.4.2	Pause	143
22.4.3	Reset	143
22.5	Setup	144
22.5.1	Presets	145
22.5.2	Dolby Dialogue Intelligence	146
22.5.3	Range	146
22.5.4	Scale / split	147
22.5.5	Other	147
<b>23</b>	<b>Leq Metering</b>	<b>148</b>
23.1	Introduction	148
23.1.1	Time-weighted sound level	148
23.1.2	Time-average sound level	148
23.1.3	Sound exposure level	149
23.2	Mic. channel Leq setup	150
23.2.1	Zero ref.	151
23.2.2	Weighting	151
23.2.3	Time-weighted F	151
23.2.4	Time-weighted S	151
23.2.5	Average integration	151
23.2.6	Main display	151
23.3	SPL	151
23.3.1	SPL reference	151
23.3.2	SPL trim	152
23.3.3	Calibrate	152

23.4	Color . . . . .	152
23.4.1	Font back . . . . .	152
23.4.2	Time-weighted F . . . . .	152
23.4.3	Time-weighted S . . . . .	152
23.4.4	Name . . . . .	152
23.4.5	Unit . . . . .	152
23.4.6	Freq. weighting . . . . .	153
23.4.7	Font blur . . . . .	153
<b>24</b>	<b>Metering History</b>	<b>154</b>
24.1	Usage . . . . .	154
24.1.1	Timecode offset . . . . .	154
24.1.2	Timecode offset reset . . . . .	154
24.1.3	Play . . . . .	155
24.2	Setup . . . . .	157
24.2.1	TimeCode . . . . .	158
24.2.2	Single curve . . . . .	158
24.2.3	Peak . . . . .	158
24.2.4	RMS . . . . .	158
24.2.5	Dynamics . . . . .	158
24.2.6	Loudness . . . . .	159
<b>25</b>	<b>Metering statistics</b>	<b>160</b>
25.1	Overview . . . . .	160
25.1.1	Peak, TruePeak and RMS . . . . .	160
25.1.2	Loudness . . . . .	161
25.2	File export . . . . .	161
25.3	Setup . . . . .	161
25.3.1	Absolute Timecode . . . . .	161
25.4	Incident Reporting . . . . .	161
25.4.1	Overview . . . . .	161
25.4.2	Setup . . . . .	162
25.5	Off-line Processing Media Queue . . . . .	163
25.5.1	Usage . . . . .	163
<b>VI</b>	<b>Spatial Analysis tools</b>	<b>165</b>
<b>26</b>	<b>Nebula surround</b>	<b>166</b>
26.1	Usage . . . . .	166
26.1.1	Speaker layout . . . . .	166
26.2	Display . . . . .	168
26.2.1	Mode . . . . .	169

26.2.2	Scale . . . . .	169
26.2.3	Power color grading . . . . .	171
<b>27</b>	<b>Vector scope</b>	<b>172</b>
27.1	Usage . . . . .	172
27.1.1	Modes in Surround : . . . . .	174
27.2	Display . . . . .	175
27.2.1	Fs . . . . .	175
27.2.2	Blending . . . . .	176
27.2.3	Fading . . . . .	176
27.2.4	Size factor . . . . .	176
27.2.5	Blur kernel size . . . . .	176
27.2.6	Color mode . . . . .	177
27.2.7	Particle start/end colors . . . . .	177
<b>VII</b>	<b>Transfer function measurement</b>	<b>178</b>
<b>28</b>	<b>Live IO</b>	<b>179</b>
28.1	Introduction . . . . .	179
28.2	Basic operation . . . . .	180
28.2.1	Compute the delay . . . . .	180
28.2.2	Compensate the delay . . . . .	180
28.2.3	Fine-tune manually . . . . .	180
28.2.4	Perform a new measurement . . . . .	180
28.3	Notes . . . . .	181
28.3.1	Max. delay time and room/venue size . . . . .	181
28.3.2	Ensure stable conditions while performing a measurement . . . . .	181
28.3.3	Limitations . . . . .	181
28.3.4	Multiple paths . . . . .	181
28.4	User interface and controls . . . . .	182
28.4.1	Name . . . . .	182
28.4.2	Ref . . . . .	183
28.4.3	Mic . . . . .	183
28.4.4	Phase invert . . . . .	183
28.4.5	On/Off . . . . .	183
28.4.6	Delay value . . . . .	184
28.4.7	Find . . . . .	184
28.4.8	Progress . . . . .	184
28.5	Setup . . . . .	185
28.5.1	Max delay . . . . .	185
28.5.2	Algorithm . . . . .	185
28.5.3	Search passes . . . . .	186

<b>29 Signal types</b>	<b>187</b>
29.1 Pink noise . . . . .	187
29.2 White noise . . . . .	187
29.3 Sine . . . . .	187
29.4 Sweep . . . . .	187
29.5 Controls . . . . .	188
29.5.1 Type . . . . .	188
29.5.2 Level . . . . .	188
29.5.3 Enable . . . . .	188
29.6 Setup . . . . .	189
29.6.1 Output . . . . .	189
29.6.2 Feed input reference . . . . .	189
29.6.3 Sine frequency . . . . .	190
29.6.4 Sweep start/end frequencies . . . . .	190
29.6.5 Sweep length . . . . .	190
29.6.6 Level . . . . .	190
<b>30 Transfer function</b>	<b>191</b>
30.1 Introduction . . . . .	191
30.2 Transfer function magnitude . . . . .	191
30.3 Transfer function coherence . . . . .	192
30.3.1 Interpretation and uses . . . . .	192
30.3.2 Display . . . . .	192
30.4 Transfer function phase . . . . .	193
30.5 Setup . . . . .	195
30.5.1 Main . . . . .	196
30.5.2 Coherence / magnitude . . . . .	197
30.5.3 Coherence . . . . .	197
30.5.4 Magnitude . . . . .	198
30.5.5 Phase . . . . .	200
30.5.6 Other . . . . .	204
<b>31 Impulse response measurement</b>	<b>205</b>
31.1 Introduction . . . . .	205
31.1.1 Analyze / freeze . . . . .	205
31.1.2 Delay Set . . . . .	206
31.1.3 Delay add . . . . .	206
31.1.4 Delay subtract . . . . .	206
31.2 General procedure . . . . .	206
31.3 Time averaging . . . . .	207
31.4 Main setup . . . . .	208
31.4.1 Run . . . . .	208
31.4.2 Reset . . . . .	208

31.5	Max length . . . . .	209
31.5.1	Time averaging . . . . .	209
31.6	Scale . . . . .	209
31.6.1	AutoRange . . . . .	209
31.7	Other . . . . .	210
31.7.1	Zoom . . . . .	210
<b>32</b>	<b>Snapshots</b>	<b>211</b>
32.1	Usage . . . . .	211
32.1.1	Snapshots . . . . .	211
32.1.2	Project . . . . .	211
32.2	Controls . . . . .	212
32.2.1	Selection and navigation . . . . .	212
32.2.2	Add new snapshot . . . . .	212
32.2.3	Acquire sweep . . . . .	213
32.2.4	Create average . . . . .	213
32.2.5	Update current . . . . .	214
32.2.6	Load project . . . . .	214
32.2.7	Curve visibility . . . . .	214
32.2.8	Color . . . . .	215
32.2.9	Name . . . . .	215
32.2.10	Invert (Iv) . . . . .	215
32.3	Setup . . . . .	215
32.3.1	Name . . . . .	216
32.3.2	Display defaults . . . . .	216
	<b>Appendices</b>	<b>217</b>
<b>A</b>	<b>Keyboard shortcuts</b>	<b>217</b>
A.1	Main . . . . .	217
A.2	Layout . . . . .	217
A.3	Snapshot . . . . .	218
A.4	Impulse Response . . . . .	219
A.5	Delay Finder . . . . .	220
A.6	Generator . . . . .	220
A.7	Meters . . . . .	220
A.8	Metering history . . . . .	220
<b>B</b>	<b>System requirements</b>	<b>221</b>
B.1	Minimum requirements . . . . .	221
B.2	Recommended configuration . . . . .	221
B.3	Common requirements . . . . .	221

B.4	Compatibility . . . . .	222
B.4.1	Operating Systems . . . . .	222
B.4.2	Hardware IO support . . . . .	222
B.4.3	Software - Sample Push support . . . . .	222
B.4.4	Supported formats . . . . .	222
<b>C</b>	<b>Release Notes</b>	<b>224</b>
C.1	FLUX:: Analyser 20.12 . . . . .	224
C.2	Major Additions . . . . .	224
C.3	Major optimizations . . . . .	224
C.4	Other Improvements . . . . .	225
C.5	Bug fixes . . . . .	225
	C.5.1 FLUX:: Analyser 20.12 . . . . .	225
	C.5.2 Sample Grabber Plug-ins 20.12 . . . . .	226
C.6	Known Issues . . . . .	226

# Welcome to FLUX:: Analyzer

22.01 version

## A User Guide

Written by Lorcan Mc Donagh

with contributions from: G el Martinet, Vincent Carlier, Florie-Anne Lafaye, Jean-Loup Pecquais & Nicolas Erard.

### Legal Information

Second edition of FLUX:: *FLUX:: Analyzer* User Guide published in April 2023

All writing is protected under copyright   2024 Harman Professional, Inc.

FLUX:: SPAT Revolution is published by  
Harman Professional, Inc.  
8500 Balboa Blvd  
Northridge, CA 91329  
United States

Copyright 2024 Harman Professional, Inc., All rights reserved.

[Product Page](#) | [Shop Page](#)

# FLUX:: Analyzer Versions

The Analyzer is available in two different software versions, The Analyzer:: Essential, and the Analyzer:: Session.

The main difference between the two are:

Analyzer:: Session

Analyzer:: Essential

Inputs/Outputs

Mono / Stereo

Mono / Stereo / MultiChannel\* up to 16.

I/O Configuration

SampleGrabber Plug-in Hardware I/O: ASIO / Core Audio

SampleGrabber Plug-in Hardware I/O: ASIO / Core Audio

Sample Rates (kHz)

44.1, 48, 88.2, 96

44.1, 48, 88.2, 96, 176.4, 192, 384 DXD

Supported Options

N/A

Live / Metering / MultiChannel

- Multichannel operation requires the Multichannel add-on option.



# Credits

## Project manager and Designer

Gael Martinet

## Developed by

Gaël Martinet, Lorcan Mc Donagh, Alexis Gentil, Bastien Prevosto, Anthony Belard, Siegfried Hand

## DSP Algorithms Specialist

Lorcan Mc Donagh

## DSP development

Gaël Martinet, Lorcan Mc Donagh

## Graphic design

Nicolas Philippot, Gaël Martinet

## Flux:: Framework development

Gaël Martinet, Florie-Anne Lafaye, Alexis Gentil, Lorcan Mc Donagh, Bastien Prevosto, Anthony Belard, Siegfried Hand, Antoine Lorence

## **additional contributions:**

Jean-Loup Pecquais, Nicolas Erard, Jean Cruypenynck, Pablo Arias, Samuel Tracol,

## **Flux:: Framework graphic engine**

Emmanuel Julien (GS lib), Gaël Martinet

## **And**

and thanks to all fantastic testers...

## **special thanks to**

Alain, Yves, Bruno and Claude for helping to shape our minds over the years

## **Dolby**

Dolby and the double-D symbol are registered trademarks of Dolby Laboratories. Dialogue Intelligence is a trademark of Dolby Laboratories All other trademarks remain the property of their respective owners.

## **FLUX::**

www.flux.audio Copyright 2024, Harman Professional, Inc. ALL RIGHTS RESERVED.

## **Additional libs**

- GS lib Emmanuel Julien, Gaël Martinet (Copyright 2013 Emmanuel Julien)
- ThorVG, Copyright (c) 2020 - 2023 notice for the ThorVG Project (see AUTHORS)
- r8brain free - Copyright (c) 2013-2023 Aleksey Vaneev
- LibJpeg - Copyright (c) 1991-2016, Thomas G. Lane, Guido Vollbeding
- libpng :
  - Copyright (c) 1995-2023 The PNG Reference Library Authors.

- Copyright (c) 2018-2023 Cosmin Truta.
- Copyright (c) 2000-2002, 2004, 2006-2018 Glenn Randers-Pehrson.
- Copyright (c) 1996-1997 Andreas Dilger.
- Copyright (c) 1995-1996 Guy Eric Schalnat, Group 42, Inc.
- Freetype 2 - Copyright (c) 2006-2023 by David Turner, Robert Wilhelm, and Werner Lemberg.
- Zlib - Copyright (c) 1995-2022 Jean-loup Gailly and Mark Adler
- bzip2 - Copyright (c) 1996-2010 Julian Seward [jseward@bzip.org](mailto:jseward@bzip.org)
- Boost - BSL-1.0
- ni-media - Copyright (c) 2022 Native Instruments
- pfft:
  - Copyright (c) 2004 the University Corporation for Atmospheric Research (“UCAR”)
  - Copyright (c) 2013 Julien Pommier ( [pommier@modartt.com](mailto:pommier@modartt.com) )
  - Copyright (c) 2019 Hayati Ayguen ( [h\\_ayguen@web.de](mailto:h_ayguen@web.de) )
  - Copyright (c) 2020 Dario Mambro ( [dario.mambro@gmail.com](mailto:dario.mambro@gmail.com) )
- pybind11 - Copyright (c) 2016 Wenzel Jakob [wenzel.jakob@epfl.ch](mailto:wenzel.jakob@epfl.ch)
- rtaudio - Copyright (c) 2001-2021 Gary P. Scavone
- rtmidi - Copyright (c) 2003-2021 Gary P. Scavone
- concurrentqueue - Copyright (c) 2013-2016, Cameron Desrochers.
- readerwriterqueue - Copyright (c) 2013-2021, Cameron Desrochers.
- assimp - Copyright (c) 2006-2021, assimp team
- enet - Copyright (c) 2002-2020 Lee Salzman
- fmt - Copyright (c) 2012 - present, Victor Zverovich and {fmt} contributors
- functions (Erik Rigtorp) - Copyright (c) 2015 Erik Rigtorp [erik@rigtorp.se](mailto:erik@rigtorp.se)
- inplace\_function - BSL-1.0
- gtest - Copyright 2008, Google Inc.
- jsoncpp - Copyright (c) 2007-2010 Baptiste Lepilleur and The JsonCpp Authors
- libcurl - Copyright (c) 1996 - 2023, Daniel Stenberg, [daniel@haxx.se](mailto:daniel@haxx.se), and many contributors
- magic\_enum - Copyright (c) 2019 - 2023 Daniil Goncharov
- nanobench - Copyright (c) 2019-2023 Martin Leitner-Ankerl
- nlohmann\_json - Copyright (c) 2013-2022 Niels Lohmann
- openddl - Copyright (c) 1999-2022 Eric Lengyel
- openvr - Copyright (c) 2015, Valve Corporation
- poly2tri - Copyright (c) 2009-2018, Poly2Tri Contributors
- pugixml - Copyright (c) 2006-2022 Arseny Kapoulkine
- rapidjson - Copyright (c) 2015 THL A29 Limited, a Tencent company, and Milo Yip.
- shared\_recursive\_mutex - Copyright (c) 2019 konanM
- sentry-native - Copyright (c) 2019 Sentry (<https://sentry.io>) and individual contributors.
- sqlite3 - Public Domain License
- sqlite\_orm - Copyright (c) 2012-2023 Eugene Zakharov and others

- stb - Copyright (c) 2017 Sean Barrett
- utfcpp - Copyright 2006 Nemanja Trifunovic
- unqlite - Copyright (c) 2012, 2013, 2014, 2015, 2016, 2017, 2018, 2019 Symisc Systems, S.U.A.R.L [M.I.A.G + Mrad Chems Eddine [chm@symisc.net](mailto:chm@symisc.net)].

## Additional Python modules

- sourcedefender - Copyright (c) 2018-2024 SOURCEdefender. All rights reserved.
- RTTrPM SDK (Blacktraxx) Copyright (c) 2019 CAST Group of Companies Inc
- argh (Andrey Mikhaylenko) - Copyright © 2010—2023 Andrey Mikhaylenko and contributors
- chardet (Mark Pilgrim, Daniel Blanchard)
- charset\_normalizer - Copyright (c) 2019 TAHRI Ahmed R.
- docopt (Vladimir Keleshev) - Copyright (c) 2012 Vladimir Keleshev, [vladimir@keleshev.com](mailto:vladimir@keleshev.com)
- dotenv - Copyright (c) 2014, Saurabh Kumar
- ecdsa (Peter Pearson) - Copyright (c) 2010 Brian Warner
- environs (Steven Loria) - Copyright 2022 Steven Loria
- ftputil (Stefan Schwarzer) - Stefan Schwarzer [sschwarzer@sschwarzer.net](mailto:sschwarzer@sschwarzer.net) and others contributors
- numpy - Copyright (c) 2005-2023, NumPy Developers.
- pendulum - Copyright (c) 2015 Sébastien Eustace
- psutil (Giampaolo Rodola) - Copyright (c) 2009, Jay Loden, Dave Daeschler, Giampaolo Rodola
- watchdog:
  - Copyright 2010 Malthe Borch [mborch@gmail.com](mailto:mborch@gmail.com)
  - Copyright 2011 Yesudeep Mangalapilly [yesudeep@gmail.com](mailto:yesudeep@gmail.com) Copyright 2012 Google, Inc & contributors.
- tgcrypto - Copyright (c) 2017-2020 Dan <https://github.com/delivrance>
- idna - Copyright (c) 2013-2022, Kim Davies and contributors. All rights reserved.
- marshmallow - Copyright 2021 Steven Loria and contributors
- packaging - Copyright (c) Donald Stufft and individual contributors.

- paramiko (Jeff Forcier) - Copyright (c) 2003-2008 Robey Pointer [robeypointer@gmail.com](mailto:robeypointer@gmail.com)
- pathtools Copyright (c) 2010 by Yesudeep Mangalapilly
- ptvsd (Microsoft) - Copyright (c) Microsoft Corporation. All rights reserved.
- pyga (Arun K.R.)
- pylightxl - Copyright (c) 2019 Viktor Kis
- pyparsing - Copyright (c) 2003-2019 Paul T. McGuire
- pytzdata - Copyright (c) 2015 Sébastien Eustace
- winshell (Tim Golden) - Copyright (c) 2012 Tim Golden
- six - Copyright (c) 2010-2020 Benjamin Peterson
- Request (Kenneth Reitz)
- sentry\_sdk - Copyright (c) 2018 Functional Software, Inc. dba Sentry
- urllib3 - Copyright (c) 2008-2020 Andrey Petrov and contributors
- certifi (Kenneth Reitz)
- anytree (c0fec0de)
- boltons - Copyright (c) 2013, Mahmoud Hashemi
- msgpack (Inada Naoki) - Copyright (c) 2008-2011 INADA Naoki [songofacandy@gmail.com](mailto:songofacandy@gmail.com)
- dateutil - Copyright 2017- Paul Ganssle [paul@ganssle.io](mailto:paul@ganssle.io) and dateutil contributors
- PyYAML (Kirill Simonov)

## Open source libraries

### RTTrPM SDK (Blacktraxx)

Copyright (c) 2019 CAST Group of Companies Inc

## **ThorVG (replaces crossed-out libraries above) - MIT**

<https://github.com/thorvg/thorvg/blob/main/LICENSE> Copyright (c) 2020 - 2024 notice for the ThorVG Project (see AUTHORS) Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions: The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software. THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **r8brain free - MIT**

<https://github.com/avaneev/r8brain-free-src/blob/master/LICENSE>

## **ooura fft from lmdsp - MIT (or MIT-like)**

<https://www.kurims.kyoto-u.ac.jp/~ooura/fft.html> Copyright Takuya OOURA, 1996-2001

## **LibJpeg - Custom (BSD-like)**

<https://jpegclub.org/reference/> Copyright (C) 1991-2016, Thomas G. Lane, Guido Vollbeding

## **libpng - PNG Reference Library License version 2**

<https://sourceforge.net/p/libpng/code/ci/master/tree/LICENSE> Copyright (c) 1995-2023 The PNG Reference Library Authors. Copyright (c) 2018-2023 Cosmin Truta. - Copyright (c) 2000-2002, 2004, 2006-2018 Glenn Randers-Pehrson. Copyright (c) 1996-1997 Andreas Dilger. Copyright (c) 1995-1996 Guy Eric Schalnat, Group 42, Inc.

## **Freetype 2 - FreeType License**

<https://github.com/freetype/freetype/blob/master/LICENSE.TXT> Copyright (C) 2006-2023 by David Turner, Robert Wilhelm, and Werner Lemberg

## **Zlib - zlib**

[https://zlib.net/zlib\\_license.html](https://zlib.net/zlib_license.html) Copyright (C) 1995-2022 Jean-loup Gailly and Mark Adler

## **bzip2 - Modified zlib**

Copyright (C) 1996-2010 Julian Seward [jseward@bzip.org](mailto:jseward@bzip.org)

## **Boost - BSL-1.0**

[https://github.com/boostorg/boost/blob/master/LICENSE\\_1\\_0.txt](https://github.com/boostorg/boost/blob/master/LICENSE_1_0.txt)

## **mimalloc - MIT**

<https://github.com/microsoft/mimalloc/blob/master/LICENSE>

## **ni-media - MIT**

<https://github.com/NativeInstruments/ni-media/blob/master/LICENSE>

## **pfft**

<https://github.com/marton78/pfft/blob/master/LICENSE.txt>

## **pybind11**

<https://github.com/pybind/pybind11/blob/master/LICENSE>

## **rtaudio**

<https://github.com/thestk/rtaudio/blob/master/LICENSE>

## **rtmidi**

<https://github.com/thestk/rtmidi/blob/master/LICENSE>

## **concurrentqueue - Simplified BSD**

<https://github.com/cameron314/concurrentqueue/blob/master/LICENSE.md> copyright (c) 2013-2016, Cameron Desrochers. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## **readerwriterqueue - Simplified BSD**

<https://github.com/cameron314/readerwriterqueue/blob/master/LICENSE.md> Copyright (c) 2013-2021, Cameron Desrochers

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.



- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## **assimp**

<https://github.com/assimp/assimp/blob/master/LICENSE> Copyright (c) 2006-2021, assimp team All rights reserved.

Redistribution and use of this software in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the assimp team, nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission of the assimp team.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION)

HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

### **enet - MIT**

<https://github.com/lzalzman/enet/blob/master/LICENSE>

### **fmt**

<https://github.com/fmtlib/fmt/blob/master/LICENSE.rst> Copyright notice Copyright (c) 2012 - present, Victor Zverovich and {fmt} contributors

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **functions (Erik Rigtorp) - MIT**

<https://github.com/rigtorp/Function/blob/master/LICENSE>

### **inplace\_function - BSL-1.0**

### **gtest - ” BSD 3-Clause “New” ” or “Revised” ”**

<https://github.com/google/googletest/blob/main/LICENSE>

## **jsoncpp - MIT**

<https://github.com/open-source-parsers/jsoncpp/blob/master/LICENSE> Copyright (c) 2007-2010 Baptiste Lepilleur and The JsonCpp Authors

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **libcurl - MIT like**

<https://curl.se/docs/copyright.html> Copyright (c) 1996 - 2024, Daniel Stenberg, daniel@haxx.se, and many contributors, see the THANKS file.

All rights reserved.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.”

## **magic\_enum - MIT**

[https://github.com/Neargye/magic\\_enum/blob/master/LICENSE](https://github.com/Neargye/magic_enum/blob/master/LICENSE) Copyright (c) 2019 - 2024 Daniil Goncharov

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **nanobench - MIT**

<https://github.com/martinus/nanobench/blob/master/LICENSE>) Copyright (c) 2019-2023 Martin Leitner-Ankerl

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **nlohmann\_json - MIT**

<https://github.com/nlohmann/json/blob/develop/LICENSE.MIT> Copyright (c) 2013-2022 Niels Lohmann

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **openddl - MIT**

<https://github.com/EricLengyel/OpenDDL/blob/main/LICENSE> Copyright (c) 1999-2022 Eric Lengyel

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **openvr - " BSD 3-Clause "New" or "Revised" "**

<https://github.com/ValveSoftware/openvr/blob/master/LICENSE> Copyright (c) 2015, Valve Corporation All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES - LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE."

## **poly2tri - " BSD 3-Clause "New" or "Revised" "**

<https://github.com/jhasse/poly2tri/blob/master/LICENSE> Copyright (c) 2009-2018, Poly2Tri Contributors All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

- Neither the name of Poly2Tri nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

### **pugixml - MIT**

<https://github.com/zeux/pugixml/blob/master/LICENSE.md> Copyright (c) 2006-2024 Arseny Kapoulkine

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **rapidjson - MIT**

<https://github.com/Tencent/rapidjson/blob/master/license.txt> - “Terms of the MIT License:

---

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions: The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software. THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **shared\_recursive\_mutex - MIT**

[https://github.com/KonanM/shared\\_recursive\\_mutex/blob/master/LICENSE](https://github.com/KonanM/shared_recursive_mutex/blob/master/LICENSE) Copyright (c) 2019 konanM

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **sentry-native - MIT**

<https://github.com/getsentry/sentry-native/blob/master/LICENSE> Copyright (c) 2019 Sentry (<https://sentry.io>) and individual contributors. All rights reserved.



Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **sqlite3 - Public Domain**

<https://www.sqlite.org/copyright.html>

### **sqlite\_orm - MIT**

[https://github.com/fnc12/sqlite\\_orm/blob/master/COMM-LICENSE](https://github.com/fnc12/sqlite_orm/blob/master/COMM-LICENSE) Copyright (c) 2012-2023 Eugene Zakharov and others

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **stb - MIT**

<https://github.com/nothings/stb/blob/master/LICENSE> Copyright (c) 2017 Sean Barrett Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions: The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software. THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **utfcpp - BSL-1.0**

<https://github.com/nemtrif/utfcpp/blob/master/LICENSE> “Boost Software License - Version 1.0 - August 17th, 2003

Permission is hereby granted, free of charge, to any person or organization obtaining a copy of the software and accompanying documentation covered by this license (the “Software”) to use, reproduce, display, distribute, execute, and transmit the Software, and to prepare derivative works of the Software, and to permit third-parties to whom the Software is furnished to do so, all subject to the following:

The copyright notices in the Software and this entire statement, including the above license grant, this restriction and the following disclaimer, must be included in all copies of the Software, in whole or in part, and all derivative works of the Software, unless such copies or derivative works are solely in the form of machine-executable object code generated by a source language processor.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR ANYONE DISTRIBUTING THE SOFTWARE BE LIABLE FOR ANY DAMAGES OR OTHER LIABILITY, WHETHER IN CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **unqlite - BSD 2-clause**

<https://github.com/symisc/unqlite/blob/master/LICENSE> ” \* Copyright (C) 2012, 2013, 2014, 2015, 2016, 2017, 2018, 2019 Symisc Systems, S.U.A.R.L [M.I.A.G Mrad Chems Eddine [chm@symisc.net](mailto:chm@symisc.net)]. \* All rights reserved. Redistribution and use in source and binary forms, with or without \* modification, are permitted provided that the following conditions \* are met: \* 1. Redistributions of source code must retain the above copyright \* notice, this list of conditions and the following disclaimer. \* 2. Redistributions in binary form must reproduce the above copyright \* notice, this list of conditions and the following disclaimer in the \* documentation and/or other materials provided with the distribution. THIS SOFTWARE IS PROVIDED BY SYMISC SYSTEMS “AS IS” AND ANY EXPRESS \* OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED \* WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR \* NON-INFRINGEMENT, ARE DISCLAIMED. IN NO EVENT SHALL SYMISC SYSTEMS \* BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR \* CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF \* SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS - OR \* BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, \* WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE \* OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN \* IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.” 3rd Party Open Source Python Modules - - - -

## **argh (Andrey Mikhaylenko) - LGPLv3**

<https://pypi.org/project/argh/>

## **chardet (Mark Pilgrim, Daniel Blanchard) - LGPL v2.1**

<https://github.com/chardet/chardet/blob/main/LICENSE>

## **charset\_normalizer - MIT**

[https://github.com/Ousret/charset\\_normalizer/blob/master/LICENSE](https://github.com/Ousret/charset_normalizer/blob/master/LICENSE) Copyright (c) 2019 TAHRI Ahmed R.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **docopt (Vladimir Keleshev) - MIT**

<https://github.com/docopt/docopt/blob/master/LICENSE-MIT> Copyright (c) 2012 Vladimir Keleshev, [vladimir@keleshev.com](mailto:vladimir@keleshev.com)

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **dotenv - “BSD 3-Clause” “New” ” or “ “Revised” “ ”**

<https://github.com/theskumar/python-dotenv/blob/main/LICENSE> Copyright (c) 2014, Saurabh Kumar (python-dotenv), 2013, Ted Tieken (django-dotenv-rw), 2013, Jacob Kaplan-Moss (django-dotenv)

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of django-dotenv nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## Open source python libraries

### ecdsa (Peter Pearson) -

<https://github.com/tlsfuzzer/python-ecdsa/blob/master/LICENSE> “python-ecdsa”  
Copyright (c) 2010 Brian Warner

Portions written in 2005 by Peter Pearson and placed in the public domain.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF

CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **environs (Steven Loria) - MIT**

<https://github.com/sloria/environs/blob/master/LICENSE> “Copyright Steven Loria

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **ffmpeg-python - Apache 2**

<https://github.com/kkroening/ffmpeg-python/blob/master/LICENSE> ” Copyright 2017 Karl Kroening

Licensed under the Apache License, Version 2.0 (the “License”) - you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an “AS IS” BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.”

## ftputil (Stefan Schwarzer) - BSD

<https://pypi.org/project/ftputil/> Copyright (c) 2004-2024 Stefan Schwarzer [sschwarzer@sschwarzer.net](mailto:sschwarzer@sschwarzer.net) and others contributors

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE”

## numpy - “BSD 3-Clause” “New” ” or “ “Revised” “ ”

<https://github.com/numpy/numpy/blob/main/LICENSE.txt> Copyright (c) 2005-2024, NumPy Developers. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above

copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

\* Neither the name of the NumPy Developers nor the names of any contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## **pendulum - MIT**

<https://github.com/sdispater/pendulum/blob/master/LICENSE> Copyright (c) 2015 Sébastien Eustace

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”



## **psutil (Giampaolo Rodola) - “BSD 3-Clause” “New” ” or “ “Revised” “ ”**

<https://github.com/giampaolo/psutil/blob/master/LICENSE> Copyright (c) 2009, Jay Loden, Dave Daeschler, Giampaolo Rodola All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the psutil authors nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES - LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## **watchdog - Apache 2**

<https://github.com/gorakhhargosh/watchdog/blob/master/LICENSE> “Copyright 2010 Malthe Borch [mborch@gmail.com](mailto:mborch@gmail.com) Copyright 2011 Yesudeep Mangalapilly [yesudeep@gmail.com](mailto:yesudeep@gmail.com) Copyright 2012 Google, Inc & contributors.

Licensed under the Apache License, Version 2.0 (the “License”) - you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an “AS IS” BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.”

### **tgcrypto - LGPL v3**

<https://github.com/pyrogram/tgcrypto/blob/master/COPYING.lesser> Copyright (C) 2017-2020 Dan <https://github.com/delivrance>

### **idna - BSD 3**

<https://github.com/kjd/idna/blob/master/LICENSE.md> Copyright (c) 2013-2023, Kim Davies and contributors. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## **marshmallow - MIT**

<https://github.com/marshmallow-code/marshmallow/blob/dev/LICENSE> “Copyright Steven Loria and contributors

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **packaging - BSD**

<https://github.com/pypa/packaging/blob/main/LICENSE> Copyright (c) Donald Stufft and individual contributors.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE

COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE”

### **paramiko (Jeff Forcier) - LGPL 2.1**

<https://github.com/paramiko/paramiko/blob/main/LICENSE> Copyright (C) 2003-2008 Robey Pointer [robeypointer@gmail.com](mailto:robeypointer@gmail.com) <https://raw.githubusercontent.com/paramiko/paramiko/main/LICENSE>

### **pathtools - MIT**

<https://github.com/gorakhargosh/pathtools/blob/master/LICENSE> Copyright (C) 2010 by Yesudeep Mangalapilly [yesudeep@gmail.com](mailto:yesudeep@gmail.com)

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **ptvsd (Microsoft) - MIT**

<https://github.com/microsoft/PTVS/blob/main/LICENSE> Copyright (c) Microsoft Corporation. All rights reserved.

Licensed under the Apache License, Version 2.0 (the “License”) - you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an “AS IS” BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.”

## **pyga (Arun K.R.) - BSD**

<https://pypi.org/project/pyga/> Copyright (c) Arun K.R. and individual contributors.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE”

## **pylightxl - MIT**

<https://github.com/PydPiper/pylightxl/blob/master/LICENSE> Copyright (c) 2019 Viktor Kis

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **pyparsing - MIT**

<https://github.com/pyparsing/pyparsing/blob/master/LICENSE> Copyright (c) 2003-2019 Paul T. McGuire Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **pytzdata - MIT**

<https://github.com/sdispater/pytzdata/blob/master/LICENSE> Copyright (c) 2015 Sébastien Eustace

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **winshell (Tim Golden) - MIT**

<https://github.com/tjguk/winshell/blob/master/LICENSE.txt> Copyright (c) 2012 Tim Golden

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **six (Copyright (c) 2010-2020 Benjamin Peterson - MIT**

<https://github.com/benjaminp/six/blob/master/LICENSE> Copyright (c) 2010-2020 Benjamin Peterson

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

## **Request (Kenneth Reitz) - Apache 2**

<https://github.com/psf/requests/blob/main/LICENSE> - modified <https://raw.githubusercontent.com/psf/requests/main/LICENSE>

## **sentry\_sdk (Copyright (c) 2018 Sentry) - MIT**

<https://github.com/getsentry/sentry-python/blob/master/LICENSE> Copyright (c) 2018 Functional Software, Inc. dba Sentry

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE



FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **urllib3 - MIT**

<https://github.com/urllib3/urllib3/blob/main/LICENSE.txt> Copyright (c) 2008-2020 Andrey Petrov and contributors.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.”

### **certifi (Kenneth Reitz) - MPL-2.0**

<https://github.com/certifi/python-certifi/blob/master/LICENSE> “This Source Code Form is subject to the terms of the Mozilla Public License, v. 2.0. If a copy of the MPL was not distributed with this file, You can obtain one at <http://mozilla.org/MPL/2.0/>.”

### **anytree (c0fec0de) - Apache 2**

<https://github.com/c0fec0de/anytree/blob/main/LICENSE>

## **boltons - BSD**

<https://github.com/mahmoud/boltons/blob/master/LICENSE> Copyright (c) 2013, Mahmoud Hashemi

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* The names of the contributors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES ; LOSS OF USE, DATA, OR PROFITS ; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.”

## **msgpack (Inada Naoki) - Apache 2**

<https://github.com/msgpack/msgpack-python/blob/main/COPYING> Copyright (C) 2008-2011 INADA Naoki [songofacandy@gmail.com](mailto:songofacandy@gmail.com)

Licensed under the Apache License, Version 2.0 (the “License”) - you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an “AS IS” BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.”

## **dateutil (Gustavo Niemeyer, Paul Ganssle) - Apache 2**

<https://github.com/dateutil/dateutil/blob/master/LICENSE> “Copyright 2017- Paul Ganssle [paul@ganssle.io](mailto:paul@ganssle.io) Copyright 2017- dateutil contributors (see AUTHORS file)

Licensed under the Apache License, Version 2.0 (the “License”) - you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an “AS IS” BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.”

## **PyYAML (Kirill Simonov) - MIT**

<https://pypi.org/project/PyYAML/> Copyright (c) Kirill Simonov.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.0

# Introduction

In a conventional digital system, audio material is captured, stored, transmitted and reproduced as a sequence of values, which correspond to the amplitude variations of an electric signal at discrete points in time. Our ability to extract meaningful information from this raw data through either hearing or visualization of the signal curve is however somewhat limited to emotional interpretation, which as one may expect, is extremely subjective.

Extensive studies have shown that first converting this data to a so-called frequency representation is extremely useful for a broad range of audio applications, as it is quite similar in principle to the human auditory system. A proper detailed explanation of the reasons behind this is well outside of the scope of this manual, so we will only hint at a few important characteristics of human hearing, namely its

- ability to recognize and isolate sounds based on their relative intensity or loudness
- ability to identify a pitch and timbre (color, texture) for sounds that fall in this category
- ability to distinguish sounds based on their actual or perceived location

A number of methods have been invented in order to translate these characteristics to measurable quantities that can be expressed in standardized units. These provide invaluable tools for assessing the quality of an audio recording, assisting the engineer in detecting potential mix problems, conforming to industry standards and requirements, calibrating loudspeaker systems, tuning room acoustics, etc.

A fundamental tool for transforming a time-based digital audio signal into a frequency-based representation, a.k.a frequency spectrum, is the discrete Fourier transform (DFT) and its derivatives, such as the Short-Term Fourier Transform (STFT) and Fast Fourier Transform (FFT). Basically, the DFT maps a signal to a set of amplitudes taken at equally-spaced frequency intervals. In essence, one can see the DFT as a bank of many band-pass filters, with as many meters at the output of these filters.

Whilst constraining the frequencies to be taken at fixed, regular intervals, is convenient both in terms of processing resources and simplicity of the computation, amongst other reasons, this linear frequency binning does not represent human hearing, which is essentially logarithmic (constant Q), very accurately. The analysis engine in FLUX:: Analyzer therefore offers both options, which are discussed in more detail in Spectrum analyzer.

# Part I


## Initial setup

# 1 SampleGrabber

## 1.1 Principle of operation

The FLUX:: Analyzer app completely separates signal acquisition from analysis for maximum flexibility.

Source and response signals are first acquired by the SampleGrabber plugin and subsequently routed across the network using the ZeroConf/Apple Bonjour protocol. Finally, the FLUX:: Analyzer standalone application receives the sample feed(s) and analyzes them.

SampleGrabber is a surround-capable plugin, available in all common format (VST, AU, RTAS and TDM), whose channel configuration is set automatically, or by clicking the  icon and setting the desired channel count in the I/O sub-menu.

The FLUX:: Analyzer application displays in the [Audio source](#) menu a list of SampleGrabber instances found on the network . Each instance is identified by the associated computer network name it is running on. Clicking a name in the list selects the corresponding SampleGrabber for input.

### Note

You can insert up to 64 instances of SampleGrabber plugins inside one same DAW, and up to 64 FLUX:: Analyzer instances can be connected to any SampleGrabber instance over the network. A SampleGrabber can be connected to up to 64 FLUX:: Analyzer instances over the network. *We do however recommend to limit the number of instances in order to avoid saturating the network.*

## 1.2 Network configuration

Network configuration is completely automatic and transparent, thanks to the use of the ZeroConf/Apple Bonjour protocol. Should you encounter any problems with your connection, we advise you to check whether the UDP port range from 46000 to 46064 is opened in your firewall, for both incoming and outgoing connections.

The audio transport requires approximately 1.4Mbps for each channel at a sample rate of 44.1kHz, whereas a 5.1 configuration at 96kHz demands a little less than 20Mbps. A properly functioning standard Ethernet 100Mbps network should therefore be more than sufficient to handle most scenarios.

**i** Note

The above bandwidth requirements naturally do not apply when using both SampleGrabber and FLUX:: Analyzer on the same machine. Please check with your network administrator if you have any bandwidth issues and/or special requirements.

## 1.3 Password

An optional password, which is a simple 4-digit number, allows you to apply light encryption to the audio stream for secure transmission over the network. It is set to 0 by default which disables encryption; in this case no additional action in the FLUX:: Analyzer application is required on your part.

If you wish to employ and define a password in SampleGrabber, please enter a matching value in the SampleGrabber menu of the FLUX:: Analyzer application in order to be able to decrypt the incoming stream.

Please note that the security level provided by this encryption is mild, and is only intended to protect from anyone eavesdropping your audio stream inside the internal network. It is not intended as a substitute for conventional network security practices and measures such as software and hardware firewalling, etc.

## 2 Typical configuration

### 2.1 Autonomous mobile configuration

#### 2.1.1 Capture

- Required:
  - Entry-level laptop.
  - Sound card with at least one stereo input available.
  - Basic DAW software for SampleGrabber signal capture, capable of using of one of the supported plugin formats.
  - Network connection.
- Optional:
  - Phantom-powered microphone input for capturing room signal in performing room acoustics measurements (Transfer function and impulse response).
  - Wireless network connection.

#### Warning

**IMPORTANT!** - The FLUX:: Analyzer Studio Session supports audio input only by using the plug-in. No hardware input/output options are supported for the FLUX:: Analyzer Session.

#### 2.1.2 Analysis

Mid-range desktop with an OpenGL/DirectX capable graphics card that meets the minimum [System requirements](#).

Capture and analysis can naturally be performed on the same machine, although you can also couple the system with a wireless transmitter to route a source test signal to the laptop in order to perform transfer curve measurements at different locations more conveniently.



## 2.2 Digital Audio Workstation

Any recent computer should be able to run FLUX:: Analyzer smoothly in a stand-alone configuration. Running your preferred DAW host application alongside with an instance of FLUX:: Analyzer naturally raises the requirements. Operating in this way will most probably require a dual-screen setup in order to be able to monitor the FLUX:: Analyzer display and DAW interface simultaneously.




Figure 2.1: SampleGrabber and FLUX:: Analyzer running on the same machine





Figure 2.2: Audio source and FLUX:: Analyzer on separate hardware

### 2.3 Avid Venue Console

SampleGrabber is available as an AAX DSP plugin, which is the preferred format when using an AVIDVenue live console. Using one or more SampleGrabber instances will free up several precious hardware outputs.

When performing transfer function and impulse response measurements, a recommended way of working is to insert a SampleGrabber on the master output and set the microphone signal as key input. This simplifies the routing and allows for fast switching between different microphones.



**i** Note

Recommended setup with Avid Venue console

# **Part II**

## **User interface**

## 3 Global presentation




Figure 3.1: Default view of the FLUX:: Analyzer

The FLUX:: Analyzer app user interface is divided in two main parts. The header and the body. In the header, you will find many options menus and parameters, while the body section display a selected arrangement of tool depending on the selected layout. It is very important to keep in mind that the FLUX:: Analyzer app is built around the concept of layout, which are factory defined regarding common audio use cases (studio, live workflow, etc.)

### 3.1 Header section

Starting from the left, we find two drop down menus:

- The source menu allows to choose which audio source you are listening to, the hardware audio interfaces hooked up to Analyzer or a SampleGrabber instances in the local network.
- The layout menu allows to changed the displayed set of tools in the body part of the app.

In the middle, there is the main toolbar, containing:

- An exit button
- An info/credit button
- An access to the main preferences menu
- An access to the user interface preferences menu
- An access to the input/ouput preferences menu
- An info button to show/hide information relative to the mouse cursor position in the main window.
- A button to open a terminal

At the formost right is disaplyed the current samplerate of the application. If any conflict is detected between the sample rate of the audio interfaces and the app, a red warning will appear at the same spot.

## 3.2 Body section

The body, or main section of the app, is designed to display various audio analysis tools. All these tools are going to be covered in further dedicated sections.

## 3.3 Mouse commands and conventions

The following mouse click actions are available:

---

Left-click	Selects the active element.
Right-click	Toggles the display of the corresponding setup menu for the item beneath the current mouse location.
Modifier + click	<b>Ctrl-click</b> is equivalent to <b>right-click</b> . Inside a setup menu item, <b>Alt-click</b> resets the corresponding setting to its default value. <b>Alt-click</b> inside an item with a zoom factor greater than one, resets the current zoom to full view (Factor = 1).

---

Double-click	Double-clicking on an editable control such as a slider or text box enters keyboard entry mode, double-clicking again validates the new value. Double-clicking anywhere inside a panel switches the panel to full-window mode, where the whole application screen is occupied by the corresponding panel; double-clicking a second time reverts to the normal layout.
Click and drag	<b>Click + drag</b> inside an item with a zoom factor greater than one shifts the current scale. <b>Alt + Click + drag</b> inside an item with a Zoom Factor allows to setup a new zoom according to the defined selection. See Figure 3.2 below.
Scroll wheel + click and drag	Turning the middle mouse wheel, if present, affects the current horizontal zoom level of the item under the cursor. Activating the wheel with the middle button simultaneously engaged shifts the current scale when the current zoom factor is greater than one.

---


## 3.4 Keyboard shortcuts

### 3.4.1 Main


---

Toggle full screen mode	Alt + Return
Display context help / credits page	F1
Reconnect network	F5
Switch to next layout	TAB
Switch to previous layout	Shift + TAB
Toggle mouse info update on/off	F6
Toggle real-time curves display	Enter / Return
Ctrl + F... Key	go to specified layout

---



(a) On spectrum



(b) On IR plots

Figure 3.2: Click and drag behavior



# 4 Header Section

## 4.1 Main toolbar

### 4.1.1 Main Setup

This is where most of the app preferences are located. The main setup menu has its own documentation section [5](#).



## 4.1.2 UI Setup




Figure 4.1: User interface setup dialog


---

Configuration	Saves / restores a complete user defined configuration.
Fonts: Small Scale	Sets the size of the smallest font used for drawing the grid labels.
Fonts: Large Scale	Sets the size of the largest font used for drawing the grid labels.
Fonts: Spectrum Peak Label	Sets the size of the font used for the Spectrum peak label.
Brightness	Adjusts global user interface brightness.
Contrast	Adjusts global user interface contrast.
Reverse color scheme	When engaged, the user interface color scheme switches from white/grey on black to black/grey on white, for improved readability in an outdoor environment.
Layout Shortcuts	This list allows you to set up to nine shortcuts for direct access to your most frequently used layouts.

---



(a) Reverse color scheme off.



(a) Reverse color scheme on.

### 4.1.3 IO Configuration Setup

The IO setup allows to access to the selection and option of the audio interface, as well as to the routing preferences. The IO setup menu has its own documentation section 6.

#### 4.1.4 Hold info text

When this button is disengaged, textual information overlays displayed above curves are held until the button is engaged again. This allows you to check a particular value precisely, such as an amplitude, gain, or phase at a particular frequency determined by the mouse cursor position when the switch was engaged. The most convenient to use this feature is to use the corresponding keyboard shortcut (*F6*).

### 4.1.5 Full-screen mode

Toggles full-screen mode on and off, to maximize screen real estate by masking the task bar (Windows) or Dock (MacOS) if desired.

### 4.1.6 Close

Exits the application.

### 4.1.7 Help / about

Displays the application credits, FLUX:: Analyzer software version number, available options with the current license, as well as a table summarizing assigned keyboard shortcuts.

## 4.2 Left toolbar

### 4.2.1 Audio source

Audio source allows you to select which source to use as input. Depending on your current configuration and settings, this will include:

- Available SampleGrabber instance(s), either local or remote.
- Available hardware device(s), if one or several sound cards are present on the host system, and the corresponding device has been selected in the Hardware IO configuration dialog.

### 4.2.2 Layout mode

FLUX:: Analyzer offers a number of user interface layouts designed and named according to typical tasks:

The layouts are grouped into categories, as described below.

---

Studio	For recording and mastering studio applications, these layouts allow simultaneous monitoring of the spectrum amplitude and spatial distribution, program level and phase.
Film mixing	Provide an overview of the signal amplitude spectrum, phase and levels. Film C & D provide Stereo Vector Scope + phase in addition.

---

Mastering	Special emphasis is put on controlling program level, spectral equilibrium and spatial image. These layouts all offer a Nebula / Spatial Spectrogram, a Vector/Surround Scope, Spectrum Amplitude and Level Meters, in different size combinations. These layouts provide the elements needed by the live sound engineer when performing speaker array calibration tasks, namely delay finder, level meter, transfer function magnitude, phase and coherence spectra, impulse response, and snapshot facilities.
Live - Show	These layouts are intended for use by a live sound engineer during the course of a show, allowing for constant monitoring of the principal level and spectral indicators of the FOH mix.
Metering statistics	Overview of all metering data at a glance.

---

**! Important**

Some layouts might not be available in your FLUX:: Analyzer edition.

### 4.3 Smoothing mode

Switches between Window (the default) and various per-octave smoothing types.

When Window type is selected, a sliding window average of adjustable width is applied to the curve, which results in more or less frequency detail being removed, depending on the Smoothing detail setting.

When any of the Octave types are selected, the average of the spectrum over the corresponding ISO bands is displayed, as series of horizontal bars. The following series are available: \* Octave \* 2/3 octave \* 1/2 octave \* 1/3 octave \* 1/6 octave \* 1/12 octave

### 4.4 Smoothing detail

Controls the amount of frequency detail of the smoothed curve, when using window smoothing. The value roughly corresponds to the maximum number of valleys and peaks that can stand out the smoothed curve. A low value lets the global tendency of the amplitude spectrum pass through, while values above 20 or so preserve more detail such as harmonics and sharp equalizer cuts and boosts. Default is 3.

- Studio A | Spectrum
- Studio B | Spectrogram
- Studio C | Scope
- Studio D | Full Spectrum
- Film | Mixing A
- Film | Mixing B
- Film | Mixing C
- Film | Mixing D
- Mastering A
- Mastering B
- Mastering C
- Mastering D
- Mastering E
- Mastering F
- Mastering G
- Mastering H
- Live A | Spectrum
- Live B | IR
- Live C | Sp / IR
- Live D | Sp / TF / IR
- Live E | Spectrogram
- Live F | Spectrum 2
- Live G | Spectrum 3
- Live H | Scope
- Live I | Show 1
- Live J | Show 2
- Metering stats

Layout	Nebula   Spatial Spectrogram	Nebula   Surround Scope	Vector Scope	Magnitude Spectrum	Spectrogram	Metering	Metering History	Metering Statistics	Wave Scope	Transfer Function	Impulse Response	Live IO	Signal Generator	Snapshot	Leq
Studio A   Spectrum	●	●				●	●								
Studio B   Spectrogram	●	●			●	●	●								
Studio C   Scope	●	●	●			●	●		●						
Studio D   Full Spectrum	●	●	●		●										
Film   Mixing A	●	●	●			●	●								
Film   Mixing B	●	●	●			●	●								
Film   Mixing C	●	●	●			●	●								
Film   Mixing D	●	●	●			●	●								
Mastering A	●	●	●			●	●								
Mastering B	●	●	●			●	●								
Mastering C	●	●	●			●	●								
Mastering D	●	●	●			●	●								
Mastering E	●	●	●		●	●	●								
Mastering F	●	●	●		●	●	●								
Mastering G	●	●	●		●	●	●								
Mastering H	●	●	●		●	●	●								
Live A   Spectrum				●		●	●			●	●	●	●	●	
Live B   IR						●	●			●	●	●	●	●	●
Live C   Sp / IR				●		●	●			●	●	●	●	●	●
Live D   Sp / TF / IR				●		●	●			●	●	●	●	●	●
Live E   Spectrogram					●	●	●			●	●	●	●	●	●
Live F   Spectrum 2				●		●	●				●	●	●	●	●
Live G   Spectrum 3				●		●	●				●	●	●	●	●
Live H   Scope								●	●		●	●	●	●	
Live I   Show 1	●	●	●			●	●								●
Live I   Show 2	●	●	●			●	●								●
Metering Stats						●	●								

(a) Layout contents matrix

(a) Available layouts

**i** Note

This curves acts as a kind of zoom-out control, as it shows the global frequency content of the signal, leaving out details such as harmonic peaks and variations imputable to transient and noise components. Typical uses for this curve is to monitor the global frequency balance of a mix and to visualize the influence of broad equalizer corrections on the mix.

## 4.5 Curve display




Toggles between the following curve display modes: \* Full: main curve only (no smoothing). \* Smoothed: smoothed curve only. \* All: both unsmoothed and smoothed curves.

**i** Note

Selecting one of the first two modes is recommended to avoid display clutter when comparing several channels and/or snapshots.

## 4.6 Max curve



The max curve employs much longer release time compared to the main curve, and as such registers short peaks much more easily.



The max curve setting controls its visibility and whether smoothing is applied: \* None: curve not displayed. \* Full: visible, unsmoothed. \* Smoothed: visible, smoothed.

**i** Note


The max curve is never displayed for snapshots, as it would be the same as the main curve, since this type of curve does not evolve in time.

## 4.7 Peak type



This setting controls the manner in which spectrum magnitude peaks are computed: \* Max (global): compute a global maximum over the entire spectrum range. \* Max (user): compute the maximum across a user defined portion of the spectrum set in the Peak range.

## 4.8 Peak label



Determines the appearance of the peak display: \* None: peaks are not shown. \* Bar (Full): vertical bar at current peak located at current frequency. \* Bar: vertical bar from base to peak value. \* Mark: text box indicating peak value, in dB, and frequency (Hz) at peak location. \* Mark + Arrow: same as above, with text at the top of the display and arrow pointing at peak location. This is the most precise indication, but takes up more space.

## 4.9 Peak range

Used in combination with the Max (user) Peak type setting, this defines the minimum and maximum frequencies to take into account when computing the peak.



# 5 Main setup

The screenshot displays the 'Preferences' window of a software application. The window is organized into several sections, each with a title and a list of settings. The settings are displayed in a dark-themed interface with orange and grey elements.

- Configuration:** A dropdown menu set to 'Default'.
- Network:**
  - Samplegrabber password: 0
  - Activity messages: On (toggle)
- Graphic engine:**
  - Engine frame rate: 60.000 fps (SMPTE x2)
- Timecode:**
  - Display frame rate: 30.000 fps (SMPTE)
  - Absolute TC: Off (toggle)
- Main:**
  - RTA block size: 8192
  - TF/Sweep Block size: 32768
  - Overlap mode: Auto (optimize CPU usage)
  - Pure spectrum: On (toggle)
  - Analysis window: BlackmanStd
  - Normalization: Coherent (sinus)
  - Scaling: Power
- Averaging:**
  - Time averaging: Off (toggle)
  - Mode: Running
  - Length: 32
- Auto-pause:**
  - Auto-pause threshold: -64 (dBFS)
- Other:**
  - Metric system: On (toggle)
  - Temperature: 20.0 (° c)

At the bottom of the window, there is a 'Reset all to default settings' button and a copyright notice: 'Copyright (c) 2023 ELLIX SE. All Rights Reserved.' The window title bar at the top right reads 'Preferences'.

Main setup dialog

## 5.1 Configuration


Save / restore a user-defined configuration to and from disk, including all the settings in this panel, as well as IO Configuration [6](#) and UI Setup [4.1.2](#).

## 5.2 SampleGrabber

### SampleGrabber password

The password entered in this field should match the one used by the SampleGrabber you wish to use as a source. This provides a reasonable level a security and prevents unauthorized access to your audio material broadcast over the network. Please take into consideration the encryption used only provides moderate protection, and is not intended to replace other security guards such as firewalls etc.

### 5.3 Graphic engine



**i** Note

Available graphic engine frame rates

Here you can specify the rate at which the display should be refreshed. Please note higher frame rates place higher demands on the GPU, and to a lesser extent, on the CPU.

The effective frame rate can be displayed by typing `SetRenderStats(1)` in the console.

## 5.4 Time code




Figure 5.1: Available display frame rates

### 5.4.1 Display frame rate

Sets the frame-rate used for time display in various parts of the program. Set it to match the frame-rate of your source material to facilitate locating time events, when working with film, TV or other time-stamped material.

### 5.4.2 Absolute Timecode

This setting toggles between absolute and relative time-code display formats. Absolute Timecode is taken from the time the application was started. Relative Timecode is the time-elapsed since the Timecode offset position. See metering history usage [24.1](#) for information on working with Timecode.

## 5.5 Main

### 5.5.1 RTA block size




Display frame rate	1024
Absolute TC	2048
	4096
RTA block size	8192
TF/Sweep Block size	16384
Overlap mode	32768
Pure spectrum	65536

Defines the size of the blocks, in samples, fed to the main spectrum analyzer engine, which is used by the spectrum magnitude, Nebula and spectrogram views.

Pure spectrum Toggles between optimized frequency analysis (default) and standard FFT.




### 5.5.2 TF/Sweep Block size



Block size used for the transfer function and snapshot performed with sine-sweep. The default is 32768, which is appropriate for most cases.


Increasing this value gives better frequency resolution, at the expense of CPU load. Lower values can be employed if you're only interested in the overall response of the analyzed system.

### 5.5.3 Overlap Mode



The overlap mode setting determines how much incoming audio frames overlap each-other. A higher overlap results in a smoother display update, at the expense of increased CPU usage. The available settings are: \* Full: highest overlap \* Auto: optimized overlap depending on available CPU resources (Default). \* Less: minimized overlap for minimal CPU usage (useful for slow machines)

### 5.5.4 Analysis window



Selects the analysis window applied to the incoming blocks.

Available choices are:

- Rectangular (None).
- Bartlett.
- Blackmann standard (default).
- Blackmann optimized.
- Hamming.
- Hann.

There is no reason to change this setting unless you have a specific reason to do so and fully understand the implications.

### 5.5.5 Normalization



Selects the normalization mode used to normalize the global gain of the spectrum display.

Available choices are:

- Coherent (sinus): 0dB peak sine gives 0dB amplitude.
- Incoherent (noise/music): 0dB RMS noise or music gives 0dB power.

### 5.5.6 Scaling




This setting controls the frequency dependent amplitude spectrum correction curve.

Available choices are:

- Amplitude: equivalent to no scaling. Amplitude of pure tones at different frequencies register at the same value. Incoming white noise is displayed as a (quasi) flat curve.
- Power (default): scaling inversely proportional to frequency ( $1/f$ ). Incoming pink noise is displayed as a flat curve.

## 5.6 Averaging



Time [20.4.4](#) averaging: engages averaging of spectrum magnitudes over time. Default is off.

### 5.6.1 Mode

- Running: the average display is updated as soon as a new incoming block arrives. This is the default.
- Fill-freeze: the display is only updated when a fresh batch of N new incoming blocks has arrived. The display is frozen until the next batch of N blocks arrive, and so on. N corresponds to the length setting defined below.

## 5.6.2 Length

The number of incoming blocks over which the resulting average spectrum is computed. Lower values lead to faster apparent display update rates, while higher values smooth-out any time-variations more. Default is 32.

Running average employs a weighting window that gives more importance to the last incoming blocks of samples. This type of time averaging is also called moving average, rolling average or running average, and is good for smoothing out abrupt variations in time and still be able to monitor in a continuous fashion. Fill-freeze mode is useful for stabilizing a flickering display while still following long-term variations, which permits a more detailed study of the curve(s). This mode is therefore useful to get a very steady picture of the spectrum while still monitoring some of the mid-term changes, and saves you from holding and resetting the display manually again and again.

## 5.7 Various

### 5.7.1 Auto-pause threshold

Analysis is paused whenever the level of any channel of the incoming audio falls below this level. Set this a tad above the acoustic and electronic noise floor of your input signal chain to retain measurements even though the audio (music program or test signal) has stopped.

### 5.7.2 Metric system

Toggle displayed units between:

- Metric system (default): distance expressed in meters, temperature in degrees Celsius.
- Imperial units: distance expressed in inches and feet, temperature in degrees Fahrenheit.

### 5.7.3 Temperature

This should be set to the ambient temperature at the current location in order to get the most accurate time to distance conversions in the delay finder and impulse response panels. The following table gives an idea of how much the speed of sound varies with temperature.

Temperature (°C)

Speed of sound (m/s)

0

331.3

15

340.31

25

346.18

35

351.96

#### **5.7.4 Preferences reset**

Resets “Default” application configuration settings to their default initial value. Please note the changes are only effective after restarting the application.



## 6 IO Configuration




Figure 6.1: IO configuration dialog


## 6.1 Configuration

Saves / restores a complete user defined configuration.



# 7 Hardware IO

## 7.1 Device



This setting lets you choose amongst a selection of devices, depending on your particular hardware configuration.

### Warning

**IMPORTANT!** - The FLUX:: Analyzer Studio Session supports audio input only by using the SampleGrabber plug-in. No hardware input/output options are supported for the FLUX:: Analyzer Session.

### 7.1.1 None

This disables hardware input and output altogether. This is the recommended choice if you do not want to take advantage of FLUX:: Analyzer's built-in audio capabilities, for example if you're working with a SampleGrabber inside a DAW or Avid Venue console setup. With some sound cards that aren't multi-client capable - meaning only one program can access it at once - disabling I/O is necessary to continue using another program simultaneously.

### 7.1.2 Your soundcard

Any installed soundcard(s) will be listed here. Under Windows, it might appear several times, in which case be sure to select the native ASIO driver for performance, not an emulated driver

which be labeled something like ASIO DirectX Full Duplex Driver, Generic Low Latency ASIO Driver or similar.

## 7.2 Sampling rate





Figure 7.1: Available sampling rates (hardware specific)

Sets the sampling rate used internally by the application. When a hardware device is selected, be sure to match this to the sampling rate set in the application panel of your soundcard control panel. We deliberately chose not to employ resampling, which in our opinion has no place in a measurement instrument. Instead we generally advise you to set your soundcard's sampling rate to 44.1k or 48k, which covers the entire audio hearing range (20-20kHz). Increasing the sampling rate above these values increases the processing power required to carry out the computations without any benefit for most practical applications.

## 7.3 Buffer size



	16
	32
Device	64
Sampling rate	128
Buffer size	256
Control panel	512
	1024
Number of channels	2048
Internal configuration: "5.1"	4096
	8192

Displays the current soundcard I/O buffer size. Depending on your soundcard, you might be able to change this to a different value directly in FLUX:: Analyzer without opening its control panel beforehand. Smaller buffer sizes leads to a shorter latency between incoming audio, display update, and audio output. This setting is certainly not as crucial as in the context of live sound processing, so there is no need to go down to extremely small values here, as this only increases the system load without offering any practical advantage.

Keep in mind a display refresh rate of 60Hz means one frame lasts for approx. 16ms, which is a bit longer than one 512 buffer at 44.1kHz, so the display will always lag less than one frame after the audio with such a setting.

## 7.4 Control panel

Opens the ASIO (Windows) / CoreAudio (MacOS) control panel for the selected soundcard driver, where you can make further settings depending on your particular hardware, such as routing, input gain etc.

# 8 Channels

## 8.1 Max number of channels



Selects the maximum number of channels to be used by the application, or equivalently the number of channels in the application I/O bus. You should set this according to the source

material format you want to analyze and visualize. This determines notably how many real-time curves are displayed in the Spectrum analyzer 16.1 view, whether the Surround scope 26.1 is displayed, etc.

**Warning**

**IMPORTANT!** - The FLUX:: Analyzer Studio Session supports only 2 channels of audio.

## 8.2 Reference configuration




Figure 8.1: Reference configurations available with 8 max. channels

Depending on the setting above, the possible standard channel configurations will be listed here, and will be a subset of the following:

- Mono (C): single center channel
- Stereo (L|R): two left-right channels
- Surround: various standard configurations depending on the exact channel count

The channels are labeled according to this configuration to make them easier to identify.

# 9 Signal generator

## 9.1 Output




Figure 9.1: Example of a output channel routing (hardware specific)

Selects one or two physical channels to which the Signal generator [29](#) output should be sent.

In case of stereo output, the signal is identical on both channels. This is provided as a facility for soundcards with minimal routing capabilities, and to avoid using a Y patch cable.



## 10 Channel 1 / Channel 2

The following group of settings are displayed for every channel selected in Channels 8. The heading displays the channel number, followed by its name, and whether it corresponds to the reference or microphone input signal for the first two channels in **?@sec-live-IO** mode.

### 10.1 Phase invert

When engaged, the phase of the corresponding channel is inverted in order to compensate for a reverse polarity somewhere else in the signal chain. Default is off.

This can happen with incorrect or non-standard wiring, when a phase switch is engaged on the preamplifier, an analog device has an odd number of inverting stages ... Use this with caution as it can compromise measurements if the “real” input signal phase does not match.

#### 10.1.1 Input

Selects which hardware device input should be routed to the corresponding internal application input.

#### 10.1.2 Output

Selects which hardware device output the corresponding internal application output should be routed to.

# **Part III**

## **System measurement**

# 11 Introduction

At first glance, an audio signal chain is very much like a series of black boxes. As an audio engineer, you can trust your ears and the manufacturer's data-sheets to assess the effects this chain has on the incoming audio. In a variety of cases, however, this is either simply impractical, not possible or not precise enough. Such situations include live sound setups, recording setups, etc., where unknown factors such as the venue's or studio's acoustic response are a crucial part of the chain.

It is therefore necessary to resort to scientific measurement procedures and tools to obtain precise, trustworthy and reproducible results. The main tools at your disposal for this purpose are transfer curve and impulse response measurement, which are especially designed for this task.


As with any measurement instrument, it is important to have a good grasp of its mode of operation as well as any possible limitations in order to use it most efficiently. Some knowledge of acoustic principles and notions of signal processing are naturally required as well. While this manual tries to cover most typical use cases and point out common do's and don't's, it obviously cannot replace neither a good textbook nor practical experience.

## 12 Initial setup

Throughout this documentation, we will refer to the measured signal processing chain as the system (sometimes called device under test in electronics literature). This system input is fed with a source signal, which produces a response signal at its output(s). Both source and response are recorded and monitored by the analyzer, from which several measurement curves are produced.

The first step is therefore to setup the measurement chain. In cases where an outboard or plugin device's characteristics are to be measured, this is just a matter of routing the inputs and outputs in your DAW.

If you're measuring the acoustic response of a physical space, you'll need to place at least one microphone at the preferred listening position to record the response. The source can either be picked up directly at the DAW output or recorded with a second microphone placed in front of the loudspeaker(s), depending on whether you want to include the loudspeaker's influence or not in the measurement.



### **i** Note

System analysis overall principle.

# 13 Practical considerations for capturing measurement signals

## 13.1 Use a measurement microphone

The goal here is to take the measurement chain out of the equation, so only specially designed microphones that exhibit a flat curve, minimal coloration, lowest noise and distortion should be used.

## 13.2 Choose a neutral preamplifier and calibrate it accurately

For the same reasons, select the most neutral preamplifier and A/D D/A converters you have at your disposal. It is especially important to be able to set accurate and reproducible gain, linear and flat response. Take special care that the signal is not so hot as to clip or distort the preamplifier input stages, as this would distort the measurements accordingly and induce you into error.

## 13.3 Maximize signal-to-noise ratio

When measuring an acoustic system, raise up the volume as high as practical for maximal signal-to-noise ratio, and try to minimize any spurious acoustic noises such as footsteps and conversation. As always, the goal is to set the test signal as high as possible above the noise floor while ensuring all devices still operate in their linear region. Finally, make sure the microphone is firmly held in position and acoustically decoupled from the floor.

In a live concert context, especially with the audience present, using a noise signal is not practical. In this case you can still perform measurements, using a music signal, but the measurements will be less accurate as the signal isn't known in advance and does not necessarily contain all frequencies like noise does.

# 14 Measurement setup




Figure 14.1: Typical configuration for a live venue measurement setup using external signal generator.




Figure 14.2: Typical configuration for a live venue measurement setup using FLUX:: Analyzer's internal signal generator and loopback

# 15 Test signals

FLUX:: Analyzer is designed to cover the broadest range of practical use cases, and does not impose a limitation on the measurement signal used.

Traditionally, transfer curve and impulse response measurements are performed by feeding a specially designed test signal into the system, the most commonly employed being pink and white noise and swept sines. While these type of signals are those that give the best and more accurate results, with each having its own strength and weaknesses, they do prohibit the measurement of a system in the context of a live system with the audience present.

Performing measurements using a live music signal allows the engineer to fine tune the system settings to compensate for changing conditions such as the effect of the crowd on acoustic reflections and damping, varying temperature and humidity, etc. Although less pleasing to the ear, we do however recommend using a noise test signal whenever possible, at least as a starting point.

You are free to use any kind of test signal generator, outboard or plugin, provided you trust it being reliable and easy to use. A selection of plugins suitable for this task is shown in the chart below.

## Note

While FLUX:: Analyzer does not impose any limitation on the test signal used, we recommend using the integrated Signal generator [29](#), which has been especially designed for this task. We conducted thorough tests on a wide panel of signal generators available as plugins or integrated into DAW software and found that many do not meet the requirements for performing accurate and reliable measurements.



# Part IV


## Spectrum analysis tools

# 16 Spectrum Analyzer


## 16.1 Presentation

The global principle and purpose of a spectrum analyzer is to transform an incoming signal, which is basically a series of amplitudes taken at successive points in time, into a series of values versus frequency. Transforming an audio signal onto a frequency scale is indeed of great interest in a wide range of tasks, and notably allows to display a global, perceptually meaningful and precise picture of the audio contents.


The display represents the so-called magnitude spectrum of the incoming signal, which is a two-dimensional curve of the magnitudes of the signal taken at frequencies ranging from 0 (DC) to half that of the current sampling rate (or Nyquist frequency in signal processing jargon). This is probably the most commonplace and most easily understood spectrum analyzer visualization, and the place where you should start most of the time when you want to inspect the frequency content of your audio material.




(a) Magnitude spectrum of a stereo signal with summing disabled, max and smoothed curves enabled



(a) Magnitude spectrum of a 5.1 surround signal sum with max and smoothed curves enabled



(a) Magnitude spectrum of a 5.1 surround signal with summing disabled



(a) Magnitude spectrum with Slide option enabled (Real time waterfall)

**Magnitude spectrum setup**

Center Right

**Range**

Max.

Min.

Auto-range  Off

**Release**

Ballistics

Max release time

**Mode**

Smoothing type

Smoothing detail

Curve display

Max curve

Peak label

Peak type

Peak range min

Peak range max

**Sum**

Filled  On

Width

Full curve color

Smoothed curve color

Max curve color

Color grading  On

**Channels**

Filled  On

Opacity

Ch. 1 curve color

Ch. 2 curve color

## 16.2 Settings

### 16.2.1 Block size

Keep in mind that the incoming audio needs to be accumulated in a buffer for a certain amount of time before the data can be computed and the display updated. In contrast with the buffers you probably know from soundcards, this block-processing is not just a computer technicality and only a source of undesirable latency, but an integral part of the process related to the mathematical aspects involved (Time-frequency product uncertainty principle).

As such, it determines both the precision of the analysis and the maximum display rate, and should be adjusted depending on the specifics of your application.

#### **i** Note

In order to maintain a sufficiently responsive display refresh rate, blocks overlap by 75 %.

The default setting is 8192 samples, which corresponds to a length of roughly 180ms at 44.1kHz sampling rate. This value constitutes a good compromise between precision and responsiveness for most situations. However, if you need to measure a particular frequency with great precision, you should raise the analysis block size. On the other hand, if you need to follow rapid spectrum variations, this value should be lowered.

### 16.2.2 Transform type

The discrete Fourier transform (DFT) is the traditional method employed to compute the frequency spectrum of a discrete digital signal. DFT can be seen as a series of notch filters centered around frequency bins that are uniformly distributed along the frequency axis, and of constant width.

The quality factor of a resonant filter, commonly denoted as  $Q$ , is defined as the ratio of its bandwidth relative to its center frequency. The DFT process is therefore analogous to a variable  $Q$  filter-bank: in other words, its frequency resolution is constant across the spectrum. When applied to sliding blocks, this process is called STFT, for Short-term Fourier transform.

Although convenient in terms of computation, this can be seen as less than ideal for many audio applications, for several reasons, the first and foremost being that human perception of frequency is known to be quasi-*logarithmic*. Logarithmic means that a two-fold increase in frequency translates to a one octave shift, a four-fold increase as a two-octave shift - and not four as this would be the case, were our perception linear in nature.

FLUX:: Analyzer employs both standard DFT and proprietary algorithms that more closely model the human perception. In addition to greatly improving the legibility of the resulting curves, this proprietary transform has the additional benefit of reducing sensitivity to noise in the high-frequency portion of the spectrum especially, and provides more stable readouts.

**i** Note

You can of course switch back to standard DFT by disengaging the Pure spectrum button.

### 16.2.3 Window type

As previously mentioned, the first step is to split the incoming signal into overlapping blocks. Each block is then multiplied with a so-called window signal prior to the spectrum computation. The purpose of this is to minimize side effects of the block processing, such as introduction of transients at the block boundaries, etc.

The window type to use is set in the Main 5 setup.

**i** Note

We suggest you leave this setting to the default unless you are quite knowledgeable with these aspects, or in the case you should need to explicitly recreate a specific measurement such as a particular method specified in a standard's document.

The [Wikipedia entry](#) on window functions in the context of signal processing is a good reference if you want to get a more thorough understanding of the subject.

**i** Note

While the windowing process is implemented in the time-domain, it can be also be seen as a smoothing filter in the frequency domain, and as such the choice of window is a compromise between frequency resolution and immunity to artifacts. Skipping the windowing process altogether, which is the same as applying a rectangular window, is not recommended. Although the rectangular window provides the best frequency resolution, it has very poor leakage characteristics.

### 16.2.4 Ballistics

The curve display update speed is controlled by the ballistics settings.

## Release time

The release time determines how fast the main curve falls back to zero. Default is 300ms.

## Max release time

The controls the release time of the optional *Max* curve, which serves to display the medium-to-long term tendency of the magnitude spectrum. Longer times mean curve maxima/peaks will be seen for a longer period.

Default is 50 seconds.

### **i** Note

The attack time is zero so the curve displays reacts instantaneously to a rising amplitude.

## 16.2.5 Averaging

This is a global setting controlled in the [Averaging](#) section of the main setup.

## 16.2.6 Frequency scaling

Scaling controls how the scaling applied to spectrum magnitudes. This is a global setting accessed through the Main [5](#) setup panel.

Scaling controls whether frequency-dependent amplitude scaling should be applied. This affects how various standard reference signals register on the display. The default *power* scaling will result in a signal with spectrum components of *constant power* registering as a flat curve, whilst amplitude will have the same effect for components of constant *amplitude* such as pure tones (sine signal).

The table below shows how the curve appearance depending on the type of input signal.  $1/f$  corresponds to a rectilinear slope on the display with both X and Y axis being logarithmic.

Input signal	Sine	White	Pink noise
Power scaling	$1/f$	$1/f$	Flat
Amplitude scaling	Flat	Flat	$1/f$

For monitoring a mix, it makes most sense to use *power* scaling, as this is the way our hearing responds. If you need to measure a room's acoustic response, an outboard unit or a plugin's

frequency response, the system magnitude transfer function is best suited for this purpose and scaling has no effect.

The *amplitude* scaling setting should therefore really be employed if you need to measure relative amplitude values, such as those of sine test tones at various frequencies. Also, note that plain DFT corresponds to scaling set to *amplitude*.

The power of a time-signal is proportional to the square of its amplitude, or equivalently, its power in dB is double the amplitude. However, in the case of a spectrum, we are measuring the output of a filter-bank, which reacts very much differently depending on the type of input signal, so the simple previous formula doesn't apply anymore.

### 16.2.7 Display range

Display range can be switched from a fixed reference interval to one that automatically adjusts to the current range of spectrum magnitude values. The latter is useful as a set and forget setting and works well to display the most vertical detail, at the expense of losing the ability to visually compare the current values to a reference level.

#### **dB Min / dB Max**

Sets the minimum and maximum magnitude to display, in decibels. This is visible the range of the display that is taken into account when auto-range is off.


Default range is -18dB (min) to -114dB (max).

#### **Range mode**

Default is *Manual*.

#### **Manual**

Uses a fixed range as specified by the above settings.



## Auto


When engaged, auto-range continuously adjusts the display to the current range of the data.

### **i** Note

A slight envelope is applied to the auto-range values in order to improve legibility, avoiding the display to follow every minor change. Peaks are always registered however, as these provide valuable information that should not be missed.

## Compressed

The range is defined by dB Min/Max values, and the Y-axis is also compressed in the lower range. This can bring out peaks and valleys in the spectrum to better visualize resonant frequencies and such.



## Compressed | Auto

Combines *Compressed* and *Auto* modes.



## 16.2.8 Summation

These settings allow you to modify the appearance of the curves in channel sum mode.

### Filled

Toggles whether the main curve is drawn as a solid-color fill or a plain line.

Default is on.

### Width

Thickness of the pen used to draw the curve lines, in pixels.

Default is 1.0.

#### Note

This setting also affects individual curves when channel sum mode is disabled.

### Full curve color

Color of the pen used to draw the main, full-detail, unsmoothed curve.

### Smoothed curve color


Color of the pen used to draw the smoothed curve.

### Max curve color

Color of the pen used to draw the max curve.

## Color grading

Applies an optional frequency-dependent coloring to the main channel-sum curve.



Magnitude spectrum with color grading enabled

### **i** Note

When enabled, any of the above fixed color settings are overridden.

## 16.2.9 Channels

This group of settings controls the appearance of curves when channel sum mode is disabled. There is one Ch.N curve color setting per channel, so you can fine-tune the color scheme employed if you wish to do so.

### Filled

Controls whether channel curves are drawn as a solid color fill or a plain line.


### Opacity

Controls the opacity of the fill when *Filled* is enabled. 100% gives a fully opaque fill, lowering this value makes the curve fill more transparent.

### Channel curve color

This setting controls the color of the curve corresponding to the nthchannel, when summation mode is disabled.

## 16.2.10 Slide (Real Time waterfall)



### Enable

Enable/disable the slide mode.

### Direction

Define the sliding Direction. From -5 to 5.

Default is 0.

### Fading

Controls display persistence, *i.e.* the “fade to black” amount for a frame. Lowering this value retains past particles longer, whereas increasing this make them disappear faster.

### Blur

Enable / Disable sliding blur.

### Blur Kernel Size

Controls the radius of the blur effect applied to past particles. Particles are “smeared” more and more as they become older, depending on this setting. Naturally, a bigger value increases the smearing, at the expense of processing power.

**i** Note

Choosing the value for this setting is really matter of taste, although please keep in mind values that above 5 will require a sufficiently powerful graphics card in order to maintain a responsive display.

### **16.2.11 Zoom**

This setting allows to check and change the current X-axis zoom level.

Default is 1.0, which corresponds to the whole frequency spectrum. Zooming with the mouse is the preferred way, as it offers more control.


# 17 Spectrogram


## 17.1 Usage

The spectrogram is a two-dimensional view of the evolution of the signal's spectrum over time, i.e. a frequency (Y-axis) versus time (X-axis) plot (or the invert, depending on the direction setting), with the magnitude modulating the color and intensity of the pixels.

A spectrogram can be computed using the STFT (short-term Fourier transform) as well as other means. It serves as a useful tool to get a global picture of how the frequency content of a signal changes over a time, and eases identification of its structure. Broadband noise appears as background, a pure tone as a horizontal line, and a transient as a vertical line.

Harmonic content appears as horizontal groups of parallel lines and vertical bars respectively, etc.






**i** Note

Example spectrogram view


## 17.2 Setup



**i** Note

Spectrogram setup

### 17.2.1 Direction



Defines the scrolling direction of the spectrogram.

### 17.2.2 Log Gain

Toggles logarithmic scaling of the magnitude spectrum on and off.

Default is on.

When enabled, the magnitude at a given time-frequency point is applied a logarithmic scaling before being converted to a pixel value. This has the effect of compressing the dynamic range, and makes low energy components stand out more, but also decreases the contrast of the display.

### 17.2.3 Threshold


#### Threshold - Range Max

Sets the maximum amplitude spectrum value to be displayed.

#### Threshold - Range Min

Sets the minimum amplitude spectrum value to be displayed.

## 17.2.4 Color Mode



### Duotone

In this color mode, the amplitude of a time-frequency point is mapped to a pixel using a two-color palette, set using start/end colors.

### Black On White

In this color mode, the amplitude of a time-frequency point is mapped to a pixel using a Black & White color palette with White as background.

### White On Black

In this color mode, the amplitude of a time-frequency point is mapped to a pixel using a Black & White color palette with Black as background.

### Power grading 1, 2, 3, 4, 5

In this color mode, the amplitude of a time-frequency point is mapped to a pixel using different predefined color palette.

### Frequency grading

In this color mode, the amplitude of a time-frequency point determines the intensity of the corresponding pixel, whose color varies according to frequency.



### **Duo-tone grading start/end colors**

Sets the color to use for minimum and maximum amplitude components respectively, when color mode is set to *Duotone*.


# 18 Nebula (spatial spectrogram)

## 18.1 Principle of operation


Nebula / Spatial Spectrogram provides a unique representation of the audio material in terms of spectral content and localization in the stereo and/or surround space. It combines the functionality of a spectrum analyzer and a vector scope in a novel real-time display. As such it provides to be an invaluable tool to get a complete and detailed overview of your mix, which you can finely tune in many aspects to suit your particular needs and preferences. A lot of work has gone into optimizing the real-time rendering of the display, not solely for aesthetic reasons, but because we wanted the display to react instantly to all the details in the incoming audio. The idea is literally for you to be able to see what you hear and feel, and not some gross simplification wrapped into shiny eye-candy, however pleasing to the eye.

The overall principles behind Nebula / Spatial Spectrogram are quite straightforward:

- At any given time, and for every frequency, the engine computes the position of a frequency in space (2D in stereo, ND for N channel-surround). This position is taken as the center of gravity of the various channels, weighted by the relative amplitude of the signal in their corresponding channel.
- A projection onto an LR-spectrum plane is computed, giving a spectrum-space frame constrained to the stereo field.
- Incoming spectrum-space frames are added back to the previous frames.
- Past frames are progressively “forgotten”, using blur and dimming, in order to make place for new information, and increase legibility.



Nebula / Spatial Spectrogram display with stereo input



Nebula / Spatial Spectrogram display with surround input



**i** Note

Nebula / Spatial Spectrogram setup options

## 18.2 Scale

### 18.2.1 Focus

Controls the stereo image width X-axis display range, in dB.

A value comprised between  $\pm 18$  and  $\pm 24$ dB correlates well with our abilities in perceiving the stereo image.

Default is  $\pm 18$ dB.

**i** Note

Pixels outside the focus range are clamped to the view boundaries.

## 18.2.2 AutoScale

This parameter controls whether the intensity of the particles are modulated by the overall audio level variations. In essence, when enabled, the color nuances will vary according to the relative amplitude of a frequency, allowing to monitor the relative amplitude spectrum variations. When disabled, the color will reflect the absolute audio level. You can also think of this as a kind of auto-gain setting.

## 18.2.3 AutoScale release

This controls whether color variations should be smoothed in time or not. When engaged, color variations is slowed down a bit, which makes overall level transitions more obvious.

You should to enable this setting when you want to visualize quick level variations such as those that frequently occur in movie soundtracks.

## 18.2.4 Linear blend range

Adds a constant blend amount to the particle. This ensures some particles are always blended into the image even if its original magnitude is low.

A low value for this setting has the effect of stabilizing the appearance of particles. With large values more of the spectrum dynamics are taken into account, and only peaks mostly come through.

## 18.2.5 Log blending

Toggles between linear and logarithmic blending of the current particle with old particles.

The default is off, i.e. linear blending, which tends to favor the display of peaks.

Logarithmic blending on the other hand preserves more of the full dynamic range of the data, and also gives some visibility to lower levels.

## 18.3 Display


### 18.3.1 Fading

Controls display persistence, i.e. the “fade to black” amount for a frame. Lowering this value retains past particles longer, whereas increasing this make them disappear faster.

### 18.3.2 Size factor

Controls the size of individual particles with respect to screen size.

### 18.3.3 Blur kernel size



Controls the radius of the blur effect applied to past particles. Particles are “smeared” more and more as they become older, depending on this setting. Naturally, a bigger value increases the smearing, at the expense of processing power.

#### **i** Note

Choosing the value for this setting is really matter of taste, although please keep in mind values that above 5 will require a sufficiently powerful graphics card in order to maintain a responsive display.

### **18.3.4 Particle scaling**



Toggles automatic adjustment of particle size with screen size. When enabled, the overall aspect of the display will remain similar even if the view size changes.

### **18.3.5 Color mode**


Provides the following particle-coloring modes: \* Power: the color varies according to the power of the signal in the frequency region \* Dynamics: same as previous except this mode works on signal dynamics \* Power / dynamics: a mix of the above \* Frequency: the color varies according to frequency only, using a rainbow-palette

## 19 Wave scope

The wave scope is a simple oscilloscope-type waveform display.







Wave scope display with stereo input.

**i** Note

The wave scope will include more functionality and settings in future releases.


## 19.1 Setup



### 19.1.1 Time

Time window in milliseconds.

## 19.1.2 Color Mode



### **Static**

Displays the waves using 1 unique static color.

### **Custom Dynamic**

Displays the waves according to the transient using a 2 user defined colors gradient.

If custom dynamic chosen, user defined Color 1 and Color 2 will be used>

### **Rainbow Dynamic**

Displays the waves according to the transient using a rainbow colors gradient.

# Part V

## Level metering tools

# 20 RMS metering

## 20.1 About Metering

All meters display the current signal meter values as solid vertical bars, and the peaks are indicated with horizontal lines at the corresponding value. Peak hold time can be adjusted in the settings if necessary. The peak value is also displayed in a numeric format at the top of the meter, which is emphasized in red in case of clipping or overload.

Several meter displays are available, each scrupulously implementing one of the more common and up-to-date industry norms, as detailed in the following paragraphs.




Figure 20.1: Meters with stereo input.




Figure 20.2: Meters with 5.1 surround input.

## 20.2 Introduction

RMS stands for Root Mean Square, is a measure of the average magnitude of a varying signal, or equivalently, the average power over the signal over a time period, called the integration time.

### **i** Note

The live layouts display dB SPL [20.4.2](#) (Sound Pressure Level) values, which is the standard measure of acoustic pressure. This requires that your input chain first be calibrated in order to get accurate and meaningful readings, as factors such as your particular microphone's sensitivity and preamplifier gain are not known in advance. For this, you will need to get your hands on a calibrator, which is a box fitted with a transducer that outputs a known acoustic level and features a socket designed to hold the microphone.

## 20.3 Preset

A number of presets covering widely and not so widely-used metering standards are provided.




Figure 20.3: Available RMS metering presets

### **20.3.1 Custom**

User defined values.

### **20.3.2 Default**

All-round settings with:

- From -48 to +18 dB range, referenced at -18dB.
- 160ms integration time, 16dB/s release, 1dB peak release and 60 frames peak hold.

### **20.3.3 Ref -18dB A/B/C/K**

Default settings with pre-equalization following either normalized ANSI A/B/C or ITU-R BS.1170-2 weighting curves, referenced to -18dB.

### **20.3.4 Ref -20dB A/B/C/K**

Default settings with pre-equalization following either normalized ANSI A/B/C or ITU-R BS.1170-2 weighting curves, referenced to -20dB.

### **20.3.5 VU meter Standard**

Standard reference VU settings, with 300ms integration, 66/7dB/s release and peak release times, referenced at 0VU/-4dBu/-18dBFS. The scale is non-linear and covers -20 to +3VU, complying with IEC 60268-17.

### **20.3.6 K-System / VU**

Linear scale, conforming to Bob Katz's recommendations, referenced at either -12, -14 or -20dB, 300ms integration, 66.7dB/s release and 12dB/s peak release times, 180 frames peak hold.

### **20.3.7 K-System / Slow**

Identical to K-System/VU, except that integration times are doubled. This reflects Bob Katz's view that Vu-meter timings are appropriate for speech, but that longer timings are better suited to music.

### **20.3.8 DIN 45406**

This preset conforms to the standard used by many European broadcasters such as French (PAD) and German (IRT) television. Integration time is 10ms for a 90% signal increase; fall-back time is 1.7s per 20dB; with a linear scale covering a range from -50 to +5dB, referenced at -9dBFS. The corresponding standards are DIN 45406, IEC 60268-1, and ARD Pfl.H.3/6.

### **20.3.9 Nordic N9**

5ms integration time for an 80% increase, fall-back time 1.7s per 20dB, linear scale covering the range from -40 to +9dB, referenced at -18dBFS, according to IEC 60268-10/1 + N9 supp.

### **20.3.10 BBC Normal**

10ms integration time for an 80% increase, fall-back time 2.8s per 24dB, custom scale with graduations spaced apart by 4dB, and 4 stands for the -18dBFS reference, according to IEC 60268-10/2a.

### **20.3.11 BBC Slow**

Same as above except for ballistics, where the integration time is changed to 69.2ms for an 80% increase, and 3.8s per 24dB fall-back.

### **20.3.12 EBU Normal**

10ms integration time for an 80% increase, fall-back time 2.8s per 24dB, linear scale covering the range from -12 to +12dB, referenced at -18dBFS, according to IEC 60268-10/2b.

### **20.3.13 EBU Slow**

Same as above except for ballistics, where the integration time is changed to 69.2ms for an 80% increase, and 3.8s per 24dB fall-back.





## 20.4 Settings

**RMS metering setup**

Preset **Default**

---

*Reference*

Zero ref. **-18 (dB)**

Weighting **None**

---

*SPL*

SPL ref. **94 (dB SPL)**

SPL trim **105 (dB)**

Calibrate **Off**

---

*Range*

Min. **-48 (dB)**

Max. **18 (dB)**

---

*Ballistics*

Integration **160.00 (ms)**

Release **16.0 (dB/s)**

Peak release **1.0 (dB/s)**

Peak hold **60**

Infinite hold **Off**

---

*Scale / split*

Unit offset **0.00 (dB)**


Unit factor **1.00**

Scale **-48;-24;-9;-6;-3;0;3;6;9;12;18**


Colors **0;6;12**

---

*Other*

start color 

end color 

Bargraph texture **On** 


## 20.4.1 Reference

### Zero reference

Adjusts the reference point. Default is -18dB (DVD standard). Do not change this unless you specifically want to divert from the standard, as this will otherwise compromise meter readings.

Standard values are -18dB for DVD authoring and -20dB for film.

### Weighting



Applies an optional weighting filter conforming to various standard curves:

- None (default).
- ITU 1770: K-weighting filter, comprising a shelving and a high-pass (RLB-weighting) filter in series, as specified in ITU-R BS.1170-2 and employed by EBU R128 (PLOUD).
- ANSI A, which is roughly the inverse of the Fletcher-Munson curve.
- ANSI B.
- ANSI C.
- ANSI D.

## 20.4.2 SPL

### SPL reference

This is the reference level of the calibrator's output, indicated on the device itself or in the corresponding datasheet. A typical value is -94dB.

## **SPL trim**

This is the offset applied to RMS dB values in order to obtain dB SPL readings. It is determined automatically by the calibration procedure.

## **Calibrate**

Press this button after having insert the microphone into the calibrator socket and activated it in order to determine the SPL trim value.

## **20.4.3 Range**

### **Min / max**

Defines the minimum and maximum values to be displayed on the meter bars. This does not affect the text readings above the bars.

## **20.4.4 Time**

### **Integration**

Defines the meter integration time constant, in milliseconds. This corresponds to the length of the time window over which an RMS level value is computed. Decrease this to respond to signal level variations more quickly, at the expense of meter precision and stability. Default is 160ms.

### **Release**

Release time of the meter, in decibels per second. This controls the falloff rate of the meter. Decrease this to respond to signal level variations more quickly, at the expense of readability. Default is 16 dB/s.

### **Peak release**

Release time of the peak indicator, in decibels per second. This controls the falloff rate of the peak hold indicators. Increase this to retain peaks for a longer time. Default is 1dB/second.

## **Peak hold**

Sets the number of display frames to wait until the peaks actually start to fall-back to zero. Default is 60 frames.

## **20.4.5 Scale & split**

### **Scale**

Meter labels are defined here as a comma separated list of dB values to be shown on the side of the meters. This also defines where to the corresponding horizontal markings. Default is -72; -40; -18; -9; -6; -3; -1; 0; 1; 3.

### **Colors**

This lets you customize the values at which color transitions occur. You can enter as many values as you wish, as a comma separated list, but make sure the values are in increasing order. Default is -9;0.

The last value always defines the clip level, which will be indicated in red.

## **20.5 Bar-graph texturing**

Controls whether meters are drawn with texture or in a plain solid color.

Default is on.

## 21 True peak metering

All digital audio wave signals are ultimately converted back to analog at some point, and while it is often desirable to maximize the overall volume of a signal or a complete mix, care must be taken in order not to go above the digital scale zero decibel ceiling, or nasty distortion and clipping will occur. This common and widely used rule is however not entirely sufficient, as the digital and analog processing involved in a D/A converter does not guarantee that a 0dBfs peak signal will exactly translate to a 0dB peak in the analog domain.

Without getting into too much detail, this phenomenon can be attributed to the over-sampling and reconstruction filters present in the D/A converters, whose role are to rebuild a continuous time signal from a set of discrete digital values sampled at regularly spaced time intervals. This interpolation process can therefore generate values which lie above 0dB, which is known as overshoot.

Relying solely on the peak value of samples can lead to the following problems:

- Inconsistent readings between successive playbacks of the same material.
- Unexpected overloads of the D/A output converter.
- Under-readings and beating of pure tones.

TruePeak metering aims to overcome these limitations by mimicking parts of the D/A conversion process, effectively up-sampling the measured signal, in order to display the true value of peaks that occur in the analog domain.





Figure 21.1: TruePeak metering setup options

## 21.1 Preset



### 21.1.1 Custom

User defined values.

### 21.1.2 Default

This preset uses the following all-round settings:

- Range: -72 ... +3 dB referenced at 0dB.
- Scale: 1.8x power factor, 0.06x reference display offset.
- Ballistics: 16dB/s release time, 1dB/s peak release, 60 frames peak hold.
- Scale / split: -72, -40, -18, -9, -6, -1, 0, +1, +3 dB.

### 21.1.3 EBU R128

Referenced at -1dB.

### 21.1.4 EBU R128 Max -3dB

Referenced at -3dB.

### 21.1.5 -48.0 -> +3

Limited -48 ... +3dB range with adapted scale/split values.



### **21.1.6 -144.5 -> +3**

Wide -144.5 ... +3dB range with adapted scale/split values, to monitor the full 24-bit dynamic range and possible clipping.

## **21.2 Settings**

### **21.2.1 Range**

#### **Min / max**

Defines the minimum and maximum values to be displayed on the meter bars. This does not affect the text readings above the bars.

#### **Ref**

Controls the position of the reference value on the display. This does not affect the meter values per se, it is a cosmetic setting only.

### **21.2.2 Scale**

#### **Power factor**

Controls the scaling of the display with respect to meter values. This allows to stretch or compress the display around Reference.

#### **Ref pixel offset factor**

Adjusts the offset of the reference value (Reference) with respect to meter height.

### **21.2.3 Time**

#### **Release**

Release speed of the meter in decibels per second.

### **Peak release**

Release speed of the peaks in decibel per second.

### **Peak hold**

Number of frames to hold the peaks, before the actual release phase begins. 60 frames corresponds to 1 second on a fast system, capable of a 60Hz refresh rate.

### **Infinite hold**

When enabled, peaks are held until the next reset, which is useful for checking a whole track never clips.

### **Reset**



button resets the meter to its initial state (values and peaks at minimum).

## **21.2.4 Scale & split**

### **Scale**

Meter labels are defined here as a comma separated list of dB values to be shown on the side of the meters. This also defines where to the corresponding horizontal markings. Default is -72;-40;-18;-9;-6;-3;-1;0;1;3.

### **Colors**

This lets you customize the values at which color transitions occur. You can enter as many values as you wish, as a comma separated list, but make sure the values are in increasing order. Default is -9;0.

The last value always defines the clip level, which will be indicated in red.

## **21.2.5 Other**

Controls whether meters are drawn with texture or in a plain solid color. Default is on.

# 22 Loudness metering

## 22.1 Loudness ITU-R BS 1770 & EBU R128 PLOUD

ITU-R BS.1170-4 and EBU R128 recommendations introduce a new paradigm for audio metering, which define a way to measure perceived loudness of audio material in a normalized and reproducible manner.

Please refer to the official documents freely available online at [tech.ebu.ch/groups/ploud](http://tech.ebu.ch/groups/ploud) \* or consult a reference book such as “[Audio Metering. Measurements, standards and practice](#)” by Eddy Brixen (Focal Press, ISBN 9780240814674) for detailed information on this subject.

## 22.2 Principles

### 22.2.1 Units

ITU-R BS.1170-2 notably defines LU (Loudness Unit) and LUFS (Loudness Unit, referenced to Full Scale) units, which are used by EBU R128, and Maximum True Peak Level.

- LU is used for measurements *relative* to a reference level and measuring range.
- LUFS is used for *absolute* measurements.

The meter display is switchable between LUFS (absolute, default) and LU (relative). The target loudness level to aim for is -23 LUFS = 0 LU.

### 22.2.2 Loudness and EBU mode

EBU mode specifies three time scales corresponding to three different, complementary loudness levels

- M: Momentary, 400ms integration time
- S: Short-term, 3s integration time
- I: Integrated from start of measurement or last reset, gated

#### **i** Note

Loudness is a measure of global loudness, so individual channel metering is not relevant in this context.

No additional slowdown of the attack or release of the meter is employed, as indicated by the norm.

The integrated loudness can be understood as the overload loudness of the audio over time, excluding very soft passages through the use of absolute and relative gating.

### **22.2.3 Loudness Range (LRA)**

Loudness range measures the average long-term variations of the loudness; it is expressed in LU.

### **22.2.4 Scales**

EBU R128 specifies two normalized scales:

- EBU +9, ranging from -18.0 LU to +9.0 LU (-41.0 LUFS to -14.0 LUFS)
- EBU +18, ranging from -36.0 LU to +18.0 LU (-59.0 LUFS to -5.0 LUFS) (Default)

## **22.3 Dolby Dialogue Intelligence**

### **22.3.1 Introduction**

While EBU R128 aims to measure global perceived loudness, irrespectively of the audio material, Dolby Dialogue Intelligence is a patented technology designed to specifically measure the perceived loudness of dialogue elements in the audio. It is therefore targeted towards broadcast applications.

### **22.3.2 General principle**

Dialogue Intelligence replaces EBU R128's level-based gate with a speech-content ratio based gate. The algorithm computes several low-level features for the incoming signal in speech channels. These are then combined into an overall speech percentage figure. When speech content is detected, Integrated Loudness is computed from the speech channels which have a speech content ratio above a certain threshold.

When other material is detected, i.e. not speech, standard EBU R128 Integrated Loudness computation is employed.

### 22.3.3 Display

The current speech content is displayed as text below the current gate status.

Additionally, color coding indicates the speech content ratio.

- Speech : speech content present
- Green: high speech content
- Orange: medium speech content
- Red: low speech content
- Other: other material present

### 22.3.4 Delay and compensation

The sophistication of the algorithms employed in Dialogue Intelligence incurs an overall latency of 2048ms (approx. 2s).

When Dialogue Intelligence is enabled, the display of other Loudness values is compensated to make sure meter readings are consistent. Other real-time meter (RMS, TruePeak) displays are not compensated, as we feel in this case maintaining the best reactivity to the incoming signal is more important.

All meter statistics are time-aligned.

### 22.3.5 Surround

Channels taken into account by the algorithm are determined based on the current channel configuration.

For mono/stereo signals, all channels are taken into account. For surround configurations, only Left/Right and Center channels are taken into account, if present.

#### **i** Note

Dialogue Intelligence computation only affects I (Integrated) Loudness values. Toggling Dialogue Intelligence on and off forces a reset of the meter values.

### 22.3.6 Copyright & patent information

Created under license from Dolby Laboratories Licensing Corporation. Use of this Software does not convey a license nor imply a right under any patent, or any other industrial or intellectual property right of Dolby Laboratories.

Dolby and the double-D symbol are registered trademarks of Dolby Laboratories. Dialogue Intelligence is a trademark of Dolby Laboratories.

#### PATENT LIST - DIALOGUE INTELLIGENCE

##### PATENTS

Country

Patent Number

AUSTRALIA

2003263845

CHINA

ZL03819918.1

FRANCE

1 532 621

GERMANY

1 532 621

HONG KONG

1073917

ISRAEL

165938

JAPAN

4585855

MEXICO

252,228

MALAYSIA

MY-133623-A

SINGAPORE

109865  
TAIWAN  
I306238  
UNITED KINGDOM  
1 532 621  
UNITED STATES  
7,454,331  
PATENT APPLICATIONS  
Country  
Application Number  
CANADA  
2,491,570  
INDIA  
1936/KOLNP/2004  
SOUTH KOREA  
2005-7003479  
UNITED STATES  
12/948,730

## **22.4 Controls and display**


### **22.4.1 Display**


The meter display has the following arrangement

- left bar: Momentary Loudness value
- right bar: Short-term Loudness
- text overlay: Integrated Loudness and Loudness Range (LU) values, Gated indicator lights red when gate is active


The Loudness Range value is displayed once measurement has been running for at least 60 seconds, according to the EBU [Tech 3342](#) specification, otherwise a ‘LRA Unstable’ warning is shown.








## 22.4.2 Pause

Clicking the  button pauses measurement; clicking again resumes it. This allows you to make adjustments without affecting Integrated Loudness, instead of having to start all over again.

## 22.4.3 Reset

Clicking the  button resets the meter to its initial state.

### Note


Don't forget to reset the Loudness meter if you're starting playback of a new track, as Integrated Loudness, by design, measures the overall Loudness since the last reset. Otherwise you'd be measuring the overall Loudness of the combined tracks, which is probably not what you want.

## 22.5 Setup



Figure 22.1: EBU R128 Loudness metering setup.

## 22.5.1 Presets



### **Custom**

Uses user-defined custom range according to min./max. values below.

### **Default**

Sets the meter to the recommended scale (EBU +18 LUFS).

### **EBU +9 LU**

Sets the meter to use EBU +9 scale in LU units.

### **EBU**

+9 LUFS Sets the meter to use EBU +9 scale in LUFS units.

### **EBU +18**

LU Sets the meter to use EBU +18 scale in LU units.

## **EBU +18 LUFS**

Sets the meter to use EBU +18 scale in LUFS units.

## **-23 LUFS Long program**

CST specification

Sets the meter to use EBU +18 scale in LUFS units with reference @ -23 LUFS and color split @-/ + 7LU from the reference.

## **-23 LUFS Short program**

CST specification

Sets the meter to use EBU +18 scale in LUFS units with reference @ -23 LUFS and Max defined 3LU up to the reference.

## **22.5.2 Dolby Dialogue Intelligence**

### **Dolby Dialogue Intelligence (TM)**

Toggles usage of Dolby Dialogue Intelligence speech gate.

### **Speech threshold**

Defines the speech content threshold in %. Speech channels with a speech content ratio below this value do not participate in the Loudness computation.

## **22.5.3 Range**

### **Min.**

Minimum Loudness to display on the bar-graphs. User adjustable.

### **Max.**

Maximum Loudness to display on the bar-graphs. User adjustable.

## 22.5.4 Scale / split

### Scale

Meter labels are defined here as a comma separated list of dB values to be shown on the side of the meters. This also defines where to the corresponding horizontal markings. Default is -72;-40;-18;-9;-6;-3;-1;0;1;3.

### Colors

This lets you customize the values at which color transitions occur. You can enter as many values as you wish, as a comma separated list, but make sure the values are in increasing order. Default is -9;0.

The last value always defines the clip level, which will be indicated in red.

## 22.5.5 Other

Controls whether meters are drawn with texture or in a plain solid color. Default is on.

# 23 Leq Metering

## 23.1 Introduction

Leq encompasses a set of sound level meter specifications, which are described in detail in the BS EN 61672-1 European Standard.

FLUX:: Analyzer implements the following Leq measurements: time-weighted sound level, time-average sound level and sound exposure level.

Frequency weighting is employed for all measurements, A being the standard and default, although other weightings can be specified if necessary.

The Leq module always measures the audio routed through the Mic channel.

### 23.1.1 Time-weighted sound level

LA is the root-mean-square sound level obtained after exponential time weighting.

Exponential averaging has the effect of progressively ‘forgetting’ past sample values.

The norm specifies two time-weighting constants:

- Fast : 125ms
- Slow: 1s

#### **i** Note

The corresponding letter symbol is LAF for an A-frequency weighted and F time-weighted sound level, for example.

### 23.1.2 Time-average sound level

Time-average sound level is basically an RMS meter with frequency-weighting applied.



### 23.1.3 Sound exposure level


This measures the sound exposure equivalent to a 'dose' received for a second.

#### **i** Note

It is useful for determining the amount of sound pressure to which listeners have been exposed for a certain duration.

This value naturally increases with time. For a constant source level, this value increases in a logarithmic fashion.

## 23.2 Mic. channel Leq setup



Mic. channel Leq setup

### **23.2.1 Zero ref.**

Adjusts the reference point. See RMS for more information.

### **23.2.2 Weighting**

Frequency weighting employed. Can be switched between ANSI standard (A, B, C, D) and none. The default is A.

### **23.2.3 Time-weighted F**

Indicates the time-constant for the Fast time-weighted sound level.

### **23.2.4 Time-weighted S**

Indicates the time-constant for the Slow time-weighted sound level.

### **23.2.5 Average integration**

Sets the integration time for the time-average sound level, between 1s and 14400s (4 hours). Default is 10s.

### **23.2.6 Main display**

Switches the main measurement display from time-average sound level (the default) to sound exposure level.

## **23.3 SPL**

### **23.3.1 SPL reference**

This is the reference level of the calibrator's output, indicated on the device itself or in the corresponding datasheet. A typical value is -94dB.

### **23.3.2 SPL trim**

This is the offset applied to RMS dB values in order to obtain dB SPL readings. It is determined automatically by the calibration procedure.

### **23.3.3 Calibrate**

Press this button after having insert the microphone into the calibrator socket and activated it in order to determine the SPL trim value.

## **23.4 Color**

The following settings control the visual aspect of the Leq display.

### **23.4.1 Font back**

Common font background color.

Main level font color. ### Level

### **23.4.2 Time-weighted F**

Fast time-weighted level font color.

### **23.4.3 Time-weighted S**

Slow time-weighted level font color.

### **23.4.4 Name**

Name font color

### **23.4.5 Unit**

Unit display font color.

### **23.4.6 Freq. weighting**

Frequency weighting type display font color.

### **23.4.7 Font blur**


Toggles font blurring on (default) and off.

# 24 Metering History

## 24.1 Usage

The metering history panel stores and displays the evolution of meters over time, with a red vertical bar indicating current time. Start and end time-points of the period over which the history are displayed left and right in time-code format.

Selecting which meters are to be included in the display is done by clicking the corresponding buttons in the setup.




### **i** Note

Metering history display.


### 24.1.1 Timecode offset

Clicking the  defines the current time as the Timecode offset.

### 24.1.2 Timecode offset reset

Clicking the  button resets the Timecode offset to zero. Absolute and relative Timecode will then be the same.

### 24.1.3 Play

Clicking the  toggles history recording on and off. Metering values are discarded when off.


#### **i** Note

The metering history relies on the same settings as those defined in the various meters. However, when multiple meter values are displayed simultaneously, the display range of the history is adapted so it encompasses the display ranges of the meters. Keep in mind different meters can be set to different zero reference points when comparing meter history curves.





## 24.2 Setup



**i** Note

Metering history setup options.

### **24.2.1 TimeCode**

#### **Absolute Timecode**

Switches between absolute and relative Timecode formats.

#### **Update Factor**

Divides the History refresh interval; allowing to increase the history time period.

### **24.2.2 Single curve**

#### **Color**

Sets the color to use when only a single curve is selected for display.

### **24.2.3 Peak**

These settings allow to specify whether Peak and/or TruePeak curves should be displayed, as well the color to use when drawing them.

### **24.2.4 RMS**

Toggle RMS curve display on and off, and specify the color to use for drawing.

### **24.2.5 Dynamics**

The dynamics is the current dynamic range of the signal, that is the ratio of the peaks with respect to the average, i.e.the crest factor of the signal.

#### **Dynamics**

Toggles dynamics curve display on and off.

## Integration

Set the integration time, in milliseconds.

## Color

Specify the color to use for drawing the curve.

### **i** Note

Percussive content such as drums or rhythm guitar exhibit high dynamics, as opposed to sustained sounds such as strings and synthesizer pads.

## 24.2.6 Loudness

These settings allow to specify whether Short-term and/or Momentary EBU R128 Loudness curves should be displayed, as well the color to use when drawing them.

## 25 Metering statistics

The metering statistics view shows a synthetic view of the current and past meter values in numeric form. It also serves to process multiple existing audio files in one pass, display and export the results to disk.



Figure 25.1: Metering statistics display

### 25.1 Overview

The display shows the average and range for the various level meter values, since the start of the application or the last time the meter was reset, in a spread-sheet type view.

#### 25.1.1 Peak, TruePeak and RMS


Mean as well as overall minimum and maximum values are shown. For min. and max. values, the corresponding Timecode position is also indicated.

## 25.1.2 Loudness


As EBU R128 Loudness already incorporates statistical computations, only the current values are shown.

## 25.2 File export

Exports a report containing a summary of the metering statistics data to a text file.

Clicking the  button brings up a standard file dialog where you can specify the desired file name for the dialog.

## 25.3 Setup



### 25.3.1 Absolute Timecode

Toggles between relative and absolute Timecode display. See [TimeCode](#) for more information.

## 25.4 Incident Reporting

### 25.4.1 Overview

All TruePeak and R128 Short term values that cross the thresholds are recorded and displayed as a list. Each row in the list shows a record of the offending peak value in dB alongside with the time-code at which the event occurred. You can navigate the list and locate the time positions of the incident, then playback again the corresponding source material in order to identify and correct the problem.

## 25.4.2 Setup




Figure 25.2: Incidents setup options.

### Max. incident count

To avoid overloading the display, and eventually, the computer's memory, there is a limit placed on the number of registered incidents, which is 2000 by default. If you go above this, it might be a good idea to back off the master fader a bit anyway to let that music breathe !

However, you can override this behavior by setting this value to -1, which will remove the limit altogether.

### TruePeak Incident Enable + threshold

Defines the threshold above which an incident will be registered. Default is 0dBTP, which corresponding to full digital scale. A conservative value would be -0.1dBTP, to be on the safe side.

Keep in mind TruePeak is designed to measure inter-sample peaks, and that 0dBTP is actually a few tenths of decibels softer than digital peak.

## **EBU R128 Short term / Dialog Incident Enable + thresholds**

Defines the threshold under/above which an incident will be registered.

## **25.5 Off-line Processing Media Queue**



### **25.5.1 Usage**

Multiple audio files can be added to the list for unattended queue processing.

#### **Principle**

The media queue is intended for processing a soundtrack possibly split across several reels and channels. Reels are processed in the order in which they are added and in which they appear in the list.

#### **Usage**

Audio files are added by clicking the icon , which brings up a standard file selection dialog, where you can select as many files as you want, provided they all have the same channel count and in a supported format, with a recognized extension (.wav). When you are ready, click the  icon to start processing the list, which will be computed much faster than real-time, especially if you have a fast computer.

The results are displayed when ready in the main view, and you can export these to a file just as you would with metering statistics computed on incoming audio.

#### **Reel grouping**

If reels are split across several multichannel files, you can add all the files at once directly in the file selection dialog. Reel order corresponds to the order in which the files were added.

## Channel grouping

If your source material consists of mono-tracks, you must add reels one-by-one, adding all files for the various channels of the current reel. Please ensure different reels have the same channel count or the software will report an error. Channel configuration and names are inferred from the file names using a fuzzy-logic algorithm that looks for the presence of typical marker characters such as **C** / Center for the center channel, **R** / Right for the right channel etc. (case insensitive).

If the automatic channel grouping does not succeed, an error message will be displayed. Please rename the offending file(s) according to one of the expected schemes above to correct the problem.

### **i** Note

This function is not intended to process unrelated soundtracks in batch mode. Please repeat the operation as necessary if you wish to obtain separate results for individual tracks.



**Part VI**

**Spatial Analysis tools**

# 26 Nebula surround

## 26.1 Usage


The Nebula | Surround scope displays a representation of how a surround signal's various components are distributed in a surround environment. The inner region displays the location of the signal frequency components in the selected surround configuration, while the outer ring shows the phase-correlation between channels.

Phase correlation between adjacent channels is shown as white section with a length proportional to the correlation. Additionally, L-R phase correlation is displayed on the top portion of the ring, and L-C and C-R inter-channel phase correlations are displayed just above the top of the ring.

Physical locations of the speakers for the selected configuration are marked on the ring itself for reference.


### 26.1.1 Speaker layout

- **Music:** this is the typical surround speaker arrangement for musical reproduction.
- **Equidistant:** this mode employs equidistant speakers arranged as an equilateral polygon.
- **Square:** this arrangement employs speakers arranged on a square.
- **Theater:** this is the typical arrangement employed in movie theaters, with redundant rear channels.



(a) Music speaker mode


(a) Equidistant speaker mode



(a) Square speaker

(a) Theater speaker

## 26.2 Display




### **i** Note

Nebula | Surround scope setup options

## 26.2.1 Mode

### Speaker mode



Selects between various commonly employed surround speaker arrangements.

### Phases

Toggles phase-correlation display on and off.

## 26.2.2 Scale

### Auto-scale

This parameter controls whether the intensity of the particles are modulated by the overall audio level variations. In essence, when enabled, the color nuances will vary according to the relative amplitude of a frequency, allowing to monitor the relative amplitude spectrum variations. When disabled, the color will reflect the absolute audio level. You can also think of this as a kind of auto-gain setting.

### Auto-scale release

This controls whether color variations should be smoothed in time or not. When engaged, color variations is slowed down a bit, which makes overall level transitions more obvious.

#### **i** Note

You should enable this setting when you want to visualize quick level variations such as those that frequently occur in movie soundtracks.

## Linear blend range

Adds a constant blend amount to the particle. This ensures some particles are always blended into the image even if its original magnitude is low.

A low value for this setting has the effect of stabilizing the appearance of particles. With large values more of the spectrum dynamics are taken into account, and only peaks mostly come through.


## Log blending

Toggles between linear and logarithmic blending of the current particle with old particles.

The default is off, i.e. linear blending, which tends to favor the display of peaks.

Logarithmic blending on the other hand preserves more of the full dynamic range of the data, and also gives some visibility to lower levels.

## Color mode



## Fading

Controls display persistence, i.e. the “fade to black” amount for a frame. Lowering this value retains past particles longer, whereas increasing this make them disappear faster.

## Size factor

Controls the size of individual particles with respect to screen size.

## Blur kernel size

Controls the radius of the blur effect applied to past particles. Particles are “smeared” more and more as they become older, depending on this setting. Naturally, a bigger value increases the smearing, at the expense of processing power.

### **i** Note

Choosing the value for this setting is really matter of taste, although please keep in mind values that above 5 will require a sufficiently powerful graphics card in order to maintain a responsive display.

## Particle factor count

Determines the amount of particles to display, relative to the default number used for the current screen size.

## Particle scaling

Toggles automatic adjustment of particle size with screen size. When enabled, the overall aspect of the display will remain similar even if the view size changes.

## Color mode

This defines how the particle color is determined: \* Power grading: color is modulated by overall signal RMS power. \* Dynamic grading: color is modulated by signal dynamics. \* Pw+Dyn grading: mix of the two previous modes. \* Freq. grading: color is modulated by frequency.

### 26.2.3 Power color grading

Determines the start and end colors used with “Power grading” color mode selected.

## 27 Vector scope

### 27.1 Usage

The vector scope tool is displayed when a stereo input is detected, otherwise the display will switch to Surround scope [26.1](#) provided if your edition of FLUX:: Analyzer includes this option.




Figure 27.1: Vector scope display in stereo.






Figure 27.2: Vector scope display in surround (with selection menu).

### 27.1.1 Modes in Surround :



#### **L-R**

Use only Left and Right Channels.

#### **Front**

Use a stereo down mix with all front channels.

#### **Rear**

Use a stereo down mix with all Rear channels.

#### **Stereo downmix**

Use a stereo down mix with all channels.

#### **Lt/Rt downmix**

Use a Lt/Rt down mix with all channels.

#### **LR-Lfe**

Use a mono summation of Left and Right + the Lfe (sub) channel.


#### **Center-Lfe**

Use Center + Lfe (sub) channel.

#### **Front-Lfe**

Use a mono summation of the front channels + the Lfe (sub) channel.


## 27.2 Display



### **i** Note

Vector scope setup options

### 27.2.1 Fs



Over-sampling factor in multiples of FS, that is the incoming audio is up-sampled as necessary to reach this multiple times 48kHz. Increasing this value increases the display precision and

reactivity, at the expense of a little CPU overhead.

### **27.2.2 Blending**

Controls the amount of particle blending with the current image, from 1 to 100%. A higher value gives more priority to the incoming audio over past frames.

### **27.2.3 Fading**

Controls display persistence, i.e. the “fade to black” amount for a frame. Lowering this value retains past particles longer, whereas increasing this make them disappear faster.

### **27.2.4 Size factor**

Controls the size of individual particles with respect to screen size.

### **27.2.5 Blur kernel size**

Controls the radius of the blur effect applied to past particles. Particles are “smeared” more and more as they become older, depending on this setting. Naturally, a bigger value increases the smearing, at the expense of processing power.

#### **i** Note

Choosing the value for this setting is really matter of taste, although please keep in mind values that above 5 will require a sufficiently powerful graphics card in order to maintain a responsive display.

## 27.2.6 Color mode



This defines how the particle color is determined: \* Static color: use only particle start color (see below) \* Power grading: color is modulated by overall signal RMS power \* Dynamic grading: color is modulated by signal dynamics \* Pw+Dyn grading: mix of the two previous modes


## 27.2.7 Particle start/end colors

Sets the particle color range to be used.

## Part VII

# Transfer function measurement

## 28 Live IO




### 28.1 Introduction

The delay finder's role is to determine the total delay of the signal path, from source to response. Note that this excludes any delays induced by your soundcard and DAW, as these should be compensated for and equivalent to zero as explained before. Here we are only concerned with the time taken by sound-pressure waves to travel the distance from loudspeakers to the measurement microphone placed at the listener position.

This figure must be determined with sample accuracy in order to establish proper transfer function and impulse response measurements. In a sound installation context, computing precise time-delay is crucial to align multiple speakers and transducers properly, as to minimize comb-filtering artifacts.


## 28.2 Basic operation

### 28.2.1 Compute the delay

Press the  button to find the delay using the most recent incoming audio. The resulting figure is displayed almost instantly as a:

- Delay in samples (smp).
- Distance in meters (m) or Imperial feet (ft.) depending on whether Metric system is enabled.
- Delay in milliseconds (ms).

### 28.2.2 Compensate the delay


Pressing the  button activates a delay line in the source signal path to compensate for the currently displayed delay value, effectively time-aligning source and response signals. Pressing again deactivates the delay line, which allows for quick comparison between uncompensated and compensated signal paths.

### 28.2.3 Fine-tune manually

If necessary, you can manually adjust the delay figure using either of these methods:

- Direct keyboard numeric value entry as time or distance figure.
- Increment / decrement by clicking the +/- icons.
- Increment / decrement using the +/- numeric keys.

### 28.2.4 Perform a new measurement

Press the  button again to perform a new measurement. This will overwrite any previous value.



## **28.3 Notes**

### **28.3.1 Max. delay time and room/venue size**

The maximum measurable delay time is adjustable in the settings. Attempting to measure a delay greater than this will inevitably lead to corrupt measurements. The default setting is 1s, which should cover the vast majority of real-world situations, since it covers a distance of 330 meters.

### **28.3.2 Ensure stable conditions while performing a measurement**

You should ensure both source and response signals have reached stability before attempting measurement. In particular, do not stop or start the audio, change the volume or any other parameter just before or during measurement. This would invalidate the measurement and you would have to start again.

### **28.3.3 Limitations**

Please note there are many unknowns in play when determining the optimum delay figure. While we did our best to make this tool as robust and accurate as possible, as with all automatic procedures there is always a possibility that it will fail. In this case you should repeat the process or resort to manual adjustment until you get satisfactory results.

### **28.3.4 Multiple paths**

The major assumption behind delay compensation is that there is a main direct path from source to listener. In a very reverberant or complex-shaped acoustic space, this obviously does not apply anymore. This is where acoustics expertise and trial-and-error comes into play, in order to attain the best compromise.

## 28.4 User interface and controls





Figure 28.1: Live IO controls.

### 28.4.1 Name




Allows to define a custom name for each channel. This is a global name; saved and restored with the preset but not directly related to the Hardware I/O Interface. As this, it will be consistent even if you switch the Hardware I/O Interface or switch to connect to a SampleGrabber 1.1.

### 28.4.2 Ref

The  button toggles whether the corresponding channel should be used as a reference signal.


Multiple channels can be used as reference, in which case a mono-sum of these channels is used as the internal reference signal.

### 28.4.3 Mic


The  button toggles whether the corresponding channel should be used as a microphone input signal, which is used to capture the response of the system.

Multiple channels can be used as microphone input, in which case a mono-sum of these channels is used as the internal microphone signal.

### 28.4.4 Phase invert

The  toggles phase inversion of the selected channel on and off. This can be used to compensate another known phase inversion somewhere else in the analog signal chain.

### 28.4.5 On/Off

The  button toggles delay compensation on and off. When the correct delay has been determined, engage this button to insert a delay line in the reference channel, to align reference and measured signals, and get correct transfer function and impulse response.

On/Off delay button appears only on channels toggled as microphone>

## 28.4.6 Delay value

The delay value is displayed simultaneously as:

- A number of samples (at the current sampling rate).
- A time delay, in milliseconds.
- A distance, in meters or feet.


You can manually adjust any of these values, using either keyboard input or fine increments with the up and down arrows; the two other values will change accordingly.

Please note precision of the distance value depends on correctness of the temperature value inserted in the main setup. In a concert hall with an audience present, there will probably important temperature variations, so this value should only be seen as a rough measure.

Lastly, remember the delay value in samples is the master value, from which others are derived.


Delay values appears only on channels toggled as microphone>

## 28.4.7 Find


Clicking the  button starts a new delay value computation. Previous values, whether computed using the delay finder or entered by hand, will be erased. The algorithm accumulates a certain amount of incoming signal before the actual computation is actually performed, to ensure the delay is always computed using the most current audio.

Find Delay appears only on channels toggled as microphone>

## 28.4.8 Progress

An informational text showing the progress of the computation is shown when the  delay find button is clicked, as well any error potentially encountered.

## 28.5 Setup




### **i** Note

Delay finder setup options.

### 28.5.1 Max delay

Sets the maximum delay that can be computed. The default is 1 second, which equates to a maximum distance between microphone and speakers of roughly 300 meters, and should be large enough for most practical applications. You can decrease this value as this minimizes the possibility of false readings.

### 28.5.2 Algorithm




Selects between three different delay finding algorithms:

- Basic: lowest CPU load, less robust to noise and interference.
- Standard: medium CPU load, the default.
- Advanced: heavy CPU load, can help in very noisy environments.

**i** Note

In the rare case where the standard method fails in your particular environment, you should try other methods.

### 28.5.3 Search passes



The delay can be set to work in one or two passes:

- Full (default): one search pass covering all possible values.
- Two-stage: first pass to determine a rough delay value, followed by a second to refine the reading.

**i** Note

Two-stage delay finding can improve accuracy in the context of an environment with heavy multiple reflections.

## 29 Signal types

### 29.1 Pink noise

Pink noise is a random signal with an amplitude falloff inversely proportional to frequency. This is the most commonly employed variety noise in audio measurement, as it a constant-energy perceived content.

### 29.2 White noise

White noise is a random signal with constant energy across the audio range. Compared to pink noise, it sounds much brighter as it has more energy in high-frequencies. Commonly employed for electronic apparatus measurements.

### 29.3 Sine

Fixed-frequency, pure tone generator.

### 29.4 Sweep

Generates a variable tone from start to end frequencies. Linear and logarithmic variants are available. Log. sweep is best suited for audio measurements as this corresponds to constant time per octave.

## 29.5 Controls





Figure 29.1: Signal generator controls.

### 29.5.1 Type



Sets the signal type to generate.

### 29.5.2 Level

Output level of the waveform, expressed in dB RMS.

### 29.5.3 Enable

Toggles signal generator output on and off.



## 29.6 Setup




Figure 29.2: Signal generator setup options.

### 29.6.1 Output

Selects the hardware output(s) to which the signal generator should be routed. Set to? None? to disable the signal generator output entirely.

#### Output 1

First generator output.

#### Output 2

Second generator output.

#### **i** Note

Both signals sent to the hardware output channels are identical.

### 29.6.2 Feed input reference

Fed the reference input (default input 1) with the signal generator.

### 29.6.3 Sine frequency

Sets the frequency of the sine generator, only applicable when the signal type is set to Sine.

### 29.6.4 Sweep start/end frequencies

Sets the range of frequencies to sweep.

#### **i** Note

Reverse start and end frequencies to obtain reverse sweep.

### 29.6.5 Sweep length

Sets the overall duration of the sweep in seconds,i.e. the time taken to go from start to end frequency.

### 29.6.6 Level

Generator output level in dB RMS.

# 30 Transfer function

## 30.1 Introduction

The transfer function of a system measures its frequency response, which is expressed in terms of magnitude and phase response. The transfer function measures the way the system affects the magnitude and phase of an incoming signal at different frequencies, and is essentially a ratio of output versus input spectra.

Practical uses of this are numerous: determining the curve of an equalizer, determining what frequencies are emphasized by an outboard device, measuring a room's acoustic response, etc.

### **i** Note

The transfer function assumes the system meets the following conditions: linearity  
time-invariance

Linearity notably implies the system is free of distortion, and time-invariance that its characteristics do not change in time.

Failing to meet these requirements will lead to unpredictable results.

In practice, the transfer function is considered an adequate measurement technique for most real-world systems, except for devices exhibiting highly non-linear behaviour such as compressors and distortion effects, and time-modulation based effects such as chorus and flanger.

## 30.2 Transfer function magnitude

The transfer function magnitude displays the gain versus frequency curve of the system under test. A pass-through obviously results in a flat horizontal line centered on 0dB. This line represents the ideal curve one would be able to achieve if all the systems defects could be compensated for, and that serves as a reference target when doing room correction.

## 30.3 Transfer function coherence

Coherence is a normalized - that is comprised between zero and one - measure of the confidence of the transfer function at a specific frequency.

In other words it describes how trustworthy the transfer function is at the corresponding frequency.

[Coherence](#) at a particular frequency indicates whether the system can accurately be described as linear gain and phase shift or not.

### 30.3.1 Interpretation and uses

Low coherence most often indicate a bad measurement, so you should look for possible causes and correct them before starting again.

Typical culprits include a noisy device, presence of distortion, channel crosstalk, acoustical noise such as cooling fans, people talking, handling noise, bad isolation from the outside, etc. Low coherence also manifests when delay is improperly compensated for.

While maximizing coherence is desirable, in most cases, it will most likely be impossible to attain a flat curve approaching unity at all frequencies, except in an anechoic chamber or very 'dead' sounding room with minimal reflections.

Reverberation, as well as mismatched transducers, tends to give lower coherence, as the signal arriving at the microphone position is really the sum of several time-delayed version of the source.

Sometimes it will be impossible to get good overall coherence, and the magnitude and phase curves will therefore be less precise, stable and smooth. This does not mean you cannot attempt extract any information from those. As always, use your judgment and knowledge of the specific system to decide which assumptions seem reasonable.

### 30.3.2 Display

By default, the transparency of the main magnitude curve is also modulated with the coherence values, which increases readability by effectively dimming untrustworthy curve portions. In addition to controls and settings identical to those of the spectrum magnitude curve, you can toggle the coherence curve on and off with the 'Enable' switch under '[Coherence](#)' in the settings.

## 30.4 Transfer function phase

**Phase** information is sometimes overlooked, and indeed it is less straightforward to understand and interpret than magnitude. Altering the phase of a signal can range from subtle to dramatic, and phase distortion can lead to temporal smearing of the audio, loss of spatial information, and other nuisances.

The transfer function phase curve displays the phase difference between output and input of the system at different frequencies, in degrees, ranging from -180 to 180.

### **i** Note

FLUX:: Analyzer employs several smoothing algorithms custom designed for phase curve smoothing, as explained in the section about **Phase** setup.

Due to the definition of phase itself and the means of computing it, the curve is generally more sensitive to extraneous noise, distortion and time-varying conditions.

Even more so than with the magnitude curve, a precisely compensated delay is critical to accurate phase computation. ~

In very reverberant environments, the phase curve will be very chaotic.

This is inevitable and a direct consequence of the complex nature of the system, and not a limitation of the instrument.

We advise to use Pure spectrum analysis mode which mitigates phase computation inaccuracies compared to plain FFT. :::




Figure 30.1: Typical transfer function display in a live room!



## 30.5 Setup



Copyright (c) 2023 FLUX:: SE, All Rights Reserved.

Figure 30.2: Transfer function setup options

Time averaging is on by default as the goal here is to provide the most stable display, and to eliminate any variations of the signal in time.

Frequency smoothing can be useful to smooth out irregularities and get a general picture of the curve. It is advised to use this function sparingly though, as it can change values by a large proportion, and obscure potential problems with either the actual system being measured, or the measurement setup itself.

A combination of time averaging and frequency smoothing is most often required to obtain readable results in real-world scenarios, especially with large rooms and outdoors.

### 30.5.1 Main

#### TF/Sweep Block size

Block size used for the transfer function and the snapshot done with sweep. The default is 32768, which is appropriate for most cases.

Increasing this value gives better frequency resolution, at the expense of CPU load. Lower values can be employed if you're only interested in the overall response of the analyzed system.



Figure 30.3: Transfer function block size

#### Time averaging

Toggles time averaging on and off. Default is on, which in most cases is necessary to provide a stable display readout.



## Length

This setting determines the number of blocks taken into account to compute the averaged transfer function. Increasing this value will give a smoother readout, but the display will react more slowly to any input variations, and CPU load will be higher.

The default is 32.

## 30.5.2 Coherence / magnitude

### Smoothing detail

Sets the amount of detail present on the smoothed magnitude and coherence curves. This number is roughly the maximum number of valleys and peaks that will remain after smoothing. A low value of around 10 is good for getting a global and uncluttered picture of a room's frequency response.

#### **i** Note

Relying on smoothed curves altogether should be avoided, as smoothing can mask-out essential information such as room modes, which materialize as sharp peaks and dips in the transfer function magnitude curve.

We strongly recommend basing your judgment on both raw and smoothed curves even when the raw curve is very noisy.

## 30.5.3 Coherence

### Enable

Toggles the display of the coherence curve on or off. With multiple snapshots, the display can rapidly become crowded, and in that case hiding the coherence curves will improve legibility. In the general case however, we recommend leaving this enabled as coherence represents important information which should not be overlooked.

### Use for curves transparency

Allows to use the coherence values to define [Magnitude](#) and [Phase](#) curves transparency.

## Display

Toggles between one of three modes:

- Full : main unsmoothed coherence curve.
- Smoothed: smoothed coherence only.
- All: both.




Figure 30.4: Available coherence display modes

## Width

Size of the pen used to draw the coherence curve.

## Color

Color of the pen used to draw the coherence curve.

## 30.5.4 Magnitude

### Range

Minimum and maximum values to which the display is clamped, in decibels.

## Display

Toggles between various combinations of raw and smoothed magnitude curve display.




Figure 30.5: Available magnitude display modes

- Full : main unsmoothed magnitude curve.
- Smoothed: smoothed magnitude only.
- All: both.

Keep in mind the smoothing process can filter out a lot of information, so relying solely on the smoothed curve should be avoided.

## Averaging mode

Choose the averaging mode of the transfer function magnitude.

Vectorial mode computes the average sum of magnitudes and magnitudes multiplied by coherence. In vectorial mode, the averaged magnitude is therefore an indication of the perceived magnitude spectrum, i.e. the sum of the direct path and diffuse field signals.

Default is RMS

## Auto-Range

Toggles auto-range on and off. When enabled, the display range automatically follows that of the transfer function magnitude curves, which is useful for hands-free operation, for example. Default is off.

## Width

Size of the pen used to draw the magnitude curve.

## Color

Color of the pen used to draw the magnitude curve.

## 30.5.5 Phase

### Phase curve specificities

You will notice the phase curve is generally very sensitive to spurious noise and interference, and that in general it requires a bit of work on your part in order to read and interpret it. Outside of the studio, in noisy places such as a live venue, phase smoothing is almost always mandatory in order to get a readable curve. It is important to understand that smoothing destroys information in order to achieve this, so you should always double-check what you see on the smoothed curve against the original, raw data.

The algorithms employed here are specific to phase, and have more options than the regular smoothing employed for spectrum magnitude, transfer function magnitude and coherence, in case you wish to fine-tune their behaviour.



## Display

Toggles between the various phase curve display modes:

- Full: raw phase only.
- Smoothed: smoothed phase only.
- All: both.

## Width

Size of the pen used to draw the phase curve.

## Color

Color of the pen used to draw the phase curve.

## Phase Smoothing

### Method

Please refer to [Phase smoothing methods](#).

### Detail

Adjusts the overall level of detail that remains after smoothing, in percent. Do not set this too low or you might miss out important information such as phase shifts at critical frequencies such as those associated with loudspeaker crossover networks.

Values around 30 are appropriated in the general case.

### Threshold

Amount of relative local phase variation that is allowed to pass through. Raising this filters out local phase curve detail, such as noise. Setting it to one suppresses all detail, whilst setting it to zero leaves the curve untouched.

0.60 is a good starting point.

## Passes

Sets the number of smoothing algorithm iterations. You can apply the smoothing process several times in order to get better results whilst still retaining local detail. Increasing this value requires more CPU processing power, so it is advised to lower this value if you find your computer cannot cope with the load. Default is 5.

## Hide jumps

When enabled, the portion of the curve that corresponds to a phase rotation is not displayed.

## Uses coherence

When enabled, frequency regions of the phase curve with low coherence are applied more smoothing. Conversely, regions with coherence close to one are applied little or no smoothing.

Low-coherence regions are caused by low signal-to-noise ratio, multiple paths, etc. which cannot be accurately described in terms of a simple gain and a phase shift anyway, so it makes sense to suppress excess detail in these regions to improve the curve's general readability.

## Method



Available phase smoothing algorithms.

The general principle is that for each curve pixel, the algorithm determines the amount of smoothing applied in its neighboring region, based on a threshold determined from other pixels in the region. The smoothing therefore adapts to the curve content, applying more smoothing in noisy regions.

StdAvg/Abs was determined to be method giving the best results in the general case, and is set as default. You might still want to experiment with other algorithms, especially if you have a slow computer.

### **Fix/Abs**

This is the simplest and least CPU-intensive phase smoothing algorithm. Smoothing uses surrounding pixels below an absolute threshold.

In practice, this means curve regions with large variations are applied stronger smoothing.

### **Fix/Rel**

Same as above, using a relative threshold.

### **Var/Abs**

A variant of first algorithm.

### **Std/Abs**

The threshold is determined from the pixels standard deviation, which is a statistical measure of data variation.

### **Std/Rel**

Same as above, using a relative threshold.

### **StdAvg/Abs**

Combination of above methods, using absolute threshold.

### **StdAvg/Rel**

Combination of above methods, using relative threshold.

 Warning

Please keep in mind the smoothing process is purely a visual aid, and is not intended to compensate for an inadequate measurement setup. In short: always rely on your ears and scientific knowledge first !

### 30.5.6 Other

#### Color grading

Apply frequency-dependent coloring to the curve. Default is off.

#### Zoom

Curve zoom ratio slider.



# 31 Impulse response measurement

## 31.1 Introduction

The impulse response of a system is the signal obtained at the output when feeding a click (also termed impulse, spike or Dirac) its input. It is a fundamental tool to describe the time properties of a linear system.


Combined with the transfer function, impulse response measurement is essential in characterizing the acoustics of a studio, concert hall or venue, from which synthetic figures such as reverberation time are derived. Determining the impulse response of an amplifier and loudspeaker in tandem can also serve to assess their performance.

A pass-through device, or equivalently, a completely dead space such as an anechoic chamber exhibit a unit impulse response, whose value at zero time is gain, and is zero at all other instants.




Figure 31.1: Impulse response display example

### 31.1.1 Analyze / freeze


The  button toggles the impulse response real-time update on and off.

### 31.1.2 Delay Set

The  delay Set button set value of the peak time location to the delay value currently set for microphone channels in the Live IO [28.1](#) panel.


If Real Time curve is disable, the Max value of the selected snapshot is used.

### 31.1.3 Delay add

The  delay add button adds value of the peak time location to the delay value currently set for microphone channels in the Live IO [28.1](#) panel.

If Real Time curve is disable, the Max value of the selected snapshot is used.

### 31.1.4 Delay subtract

The  delay subtract button subtracts the peak value to the microphone channels delay.

If Real Time curve is disable, the Max value of the selected snapshot is used.

#### Note

The impulse response is closely tied to the transfer function, in that they are both related to another by a Fourier transform.

For practical aspects, FLUX:: Analyzer employs two distinct analysis engines to compute the impulse response and transfer function, as this allows to use separate settings for the two, which is often necessary in practice.

## 31.2 General procedure

Impulse response (IR) measurement requires that sufficient samples be accumulated before the actual computation is ready, depending on the values of the Max Length and Time averaging [31.3](#) settings. The user interface displays a message indicating the remaining time before the display is ready, whenever the related settings are changed or the reset button is pressed.

Because the software cannot detect whenever you make changes to the analyzed system, you need to press the Reset button in the setup or wait for the display to stabilize before reading the display.

Once your test setup is ready, press the 'Reset' button and wait for the display showing remaining time to disappear, at which point the IR display is ready. When a sufficient amount of samples has been accumulated, IR computation goes on as long as the 'Run' button is active, and is updated with new incoming samples.

**i** Note

Make sure the actual impulse response is shorter than the maximum specified time, otherwise mild to severe time-aliasing will occur, and the measurement will not be reliable. A good rule of thumb is to set the Max length parameter to twice that of the estimated RT60 of the room.

If in doubt, raise the Max length setting until the impulse response curve does not change, and check the tail of the curve does indeed fall to zero.

### 31.3 Time averaging

The time averaging function computes the mean of several IR measurements over time, which is very useful to filter out noise and other artifacts. It is enabled by default as this gives better display stability and measurement robustness, however averaging also slows down the reactivity of the display to incoming variations, so you can disable it if needed.

When IR averaging is enabled, a message is shown giving the number of currently computed impulse responses versus averaging length. The display switches to show the mean confidence percentage when ready.

## 31.4 Main setup



Impulse response setup options

### 31.4.1 Run

Toggles impulse response live update on and off. Default is on. You can temporarily freeze the impulse response with this button, to examine it in detail at your leisure, without worrying about changing external conditions.

Disabling 'Run' is equivalent to freezing the measurement, and leaves the averaging buffer as is.

### 31.4.2 Reset

Resets the impulse response computation, including the averaging buffer.

### **i** Note

If you are using a lengthy averaging setting and have just changed your setup, you can reset the entire impulse response to immediately forget previous measurements .

## **31.5 Max length**

Sets the maximum length of the impulse response in seconds. If the reverberation time in your room exceeds this value, time-aliasing will occur, meaning that the impulse response computation will be incorrect and some of the reverberation tail might end up at the start of the display. The default value is 0.3s.

Increasing this value not only requires more processing power, it also increases the time needed to wait for the display to be updated, as the calculations involved need a greater amount of incoming audio samples to be processed.

Combining time averaging and a long length setting mean you'll have to wait 30 seconds or so for the display to stabilize, so you should really do this if you need to or do not mind waiting.

### **31.5.1 Time averaging**

Accumulates several impulse response measurements and averages them before display. This allows for more precise measurements and lessens the effect of spurious acoustic noise interfering with the measurement, but it also means having to wait longer for the measurement to be ready.

## **31.6 Scale**

### **31.6.1 AutoRange**

Toggles auto-scaling the vertical axis to the effective range of the impulse response data in the current timeframe. It functions as an automatic zoom alongside the vertical axis, which can provide useful for hands-free operation.

## **31.7 Other**

### **31.7.1 Zoom**

#### **Zoom X**

Adjusts the horizontal axis zoom factor, which can also be changed by clicking inside the impulse response display itself and rotating the mouse center wheel up and down (scroll in / out), if your mouse has this feature.

#### **Zoom Y-/+**

Adjusts the vertical axis zoom factor.

## 32 Snapshots

Curves can be saved on disk for subsequent loading, allowing for comparison between mixes, comparison to a reference spectra, etc.

A snapshot contains the state of the curves at the time it was taken:

- Channel spectra.
- Transfer function.
- Impulse response.

A snapshot, as implied by the name, is like a picture of the whole application at a given time. A snapshot contains all the data to save the current signal analysis as displayed on screen, and restore it at any given time, as well as to make comparisons between different locations, setups, etc.

### 32.1 Usage

#### 32.1.1 Snapshots

Any number of snapshots can be stored and recalled for further use, and are organized into a group container called a project.

Please keep in mind computing and displaying the data associated with a snapshot is not free in terms of processing power and memory. How many snapshots you can use at a time will depends on your particular configuration.

#### 32.1.2 Project

FLUX:: Analyzer creates a default project at startup, which the snapshots will be added to. Projects are stored on disk as a folder containing associated data files. Projects can therefore be renamed, moved, archived and transferred between computers using any method you wish, provided you include all data files inside the project folder.

You can save and reload as many projects as you want, disk space permitting.

Projects are saved in

<User folder>/FLUX SE/Pure Analyzer System/Data/<Project Name> >

## 32.2 Controls




Figure 32.1: Snapshot list and controls


The snapshot area shows a list view, where one or more snapshots can be selected. The selected snapshot(s) will be highlighted accordingly, both in the list and the corresponding display(s), with increased curve thickness.

### 32.2.1 Selection and navigation

The snapshot list follows standard user interface guidelines, which means you can:


- Use keyboard up and down arrows to change the currently selected snapshot. Note: the snapshot section area must be in focus for this to have effect.
- Click on any snapshot to select it.
- **Shift + click** to define a selection range of multiple snapshots.

### 32.2.2 Add new snapshot

Clicking the  icon immediately creates a new snapshot, stores it on disk, in the folder, adds it to the current project and selects it.



### 32.2.3 Acquire sweep

The  button launches acquisition of a sweep snapshot. This special type of snapshot automates the acquisition of transfer function and impulse response curves using a swept sine generator output.

Please check the following for proper operation:


- **Generator output -Chapter 29** should be properly assigned to the corresponding hardware channels .
- Hardware IO should be properly configured and set to hardware output(s).
- Sweep start/end frequencies should be set as desired.

Providing the previous requirements are met, a progress dialog will then be displayed until all data has been acquired and the snapshot is computed and ready for display.

#### Note

Ensure the outputs of the generator and the connected speakers are set to reasonable levels in order to prevent damage to your equipment and hearing loss.

### 32.2.4 Create average

Click the  button with multiple snapshots selected to create a new snapshot average of these.

The new snapshot curve data is computed from the selected snapshot data as follows:

- Spectrum magnitude: average of magnitude vectors.
- Transfer function magnitude: average of magnitude vectors.
- Transfer function phase is set to zero as there is no mathematically significant meaning to averaging of potentially unrelated phase spectra.
- Transfer function coherence: average of coherence vectors.
- Impulse response: average of signals.

The averaging can only be performed if the snapshots are compatible with one another, that is they have identical:


- Sampling rate.
- Number of channels.
- Spectrum type.
- Impulse response length.

A warning message will inform you the averaging cannot be performed if one of the above conditions are not met.

**i** Note

The snapshot average stores the average of the snapshots at the moment it was created. If you change the snapshots in any way, the snapshot average will not change.

### 32.2.5 Update current

Clicking the  button will overwrite the last selected snapshot contents with the most current data.

This is especially useful when you are fine-tuning your measurement setup and only want to keep the latest one, without creating several snapshots and deleting them afterwards.

**i** Note

This function is destructive: there is no means to revert the original snapshot data.

### 32.2.6 Load project

Opens a dialog box where you can select an existing folder containing a previously saved project.

To create a new empty project, creating a new folder and name it, then selecting using in this dialog.

### 32.2.7 Curve visibility

For each snapshot, you can control which curve should be displayed. These controls are intended to select only those curves that you really need to be displayed when there are many visible snapshots, and still maintain a legible display:

- Transfer function coherence.
- Transfer function magnitude.
- Transfer function phase.
- Magnitude spectrum.
- Impulse response.

**i** Note

The default visibility of newly created curves can be customized in Display defaults.

### 32.2.8 Color

Opens up a color selector dialog where you can manually set the color used to identify the snapshot, both in the list and as a curve.


### 32.2.9 Name

By the default, newly created snapshots are given the name unlabeled-x, where x is the current number of snapshots in the project. You are strongly encouraged to edit this name for further reference.

### 32.2.10 Invert (lv)

Inverts the magnitude curve of the Transfer function.

## 32.3 Setup



**i** Note

Snapshot setup options

### 32.3.1 Name

You can here define a new project name which will ultimately create a new folder in the user data folder <User folder>/FLUX SE/Pure Analyzer System/Data/<Project Name>

### 32.3.2 Display defaults

Toggles the default curve visibility applied to newly created snapshots.

‘All’ controls whether new snapshots should be visible by default, and you can fine-tune which curves should also be shown/hidden here.

# A Keyboard shortcuts

## A.1 Main

Toggle full screen mode

Alt + Return

Display context help / credits page

F1

Reconnect network

F5

Switch to next layout

TAB

Switch to previous layout

Shift + TAB

Toggle mouse info update on/off

F6

Toggle real-time curves display

Enter / Return

## A.2 Layout

Ctrl + F... Key

go to specified layout

## A.3 Snapshot

Create new snapshot

Space

Create new sweep snapshot

Shift + Space

Create new average snapshot

Windows: Ctrl + Shift + Space

macOS: alt + Space

Update first selected snapshot

Windows: Ctrl + Space

macOS: Ctrl + Shift + Space

Delete selected snapshot(s)

Delete

Load snapshot project

Ctrl + O

Export selected snapshot(s)

Ctrl + S

Select all snapshots

Ctrl + A

De-select all snapshots

Escape

Select next snapshot

Down Arrow

Select previous snapshot

Up Arrow

Add next snapshot to selection

Shift + Down

Add previous snapshot to selection

Shift + Up

Select first snapshot

Home

Select last snapshot

End

Toggle selected snapshot Main curve on/off

0

Toggle selected snapshot Coherence curve on/off

1

Toggle selected snapshot Mag curve on/off

2

Toggle selected snapshot Phase curve on/off

3

Toggle selected snapshot Spectrum curve on/off

4

Toggle selected snapshot IR curve on/off

5

## **A.4 Impulse Response**

Add delay

Ctrl + Add (NUMPAD +)

Subtract delay

Ctrl + Subtract (NUMPAD -)

## **A.5 Delay Finder**

Increment delay by one sample

Add (NUMPAD +)

Decrement delay by one sample

Subtract (NUMPAD -)

Find delay

Ctrl + F

Reset delay

Ctrl + NUMPAD 0

Compensate delay

Ctrl + D

## **A.6 Generator**

Toggle generator on/off

G

## **A.7 Meters**

Refresh all meters

M

## **A.8 Metering history**

Set Timecode offset

T

Reset Timecode offset

R



## B System requirements

FLUX:: Analyzer is built around FLUX::SE's new 2D/3D efficient graphic engine, which employs full GPU-acceleration using an OpenGL-compliant graphics card.

In order to experience the outstanding responsiveness with the Analyzer, even with a very busy display, and to fully take advantage of the software's analysis capabilities, using a modern nVidia or ATI Radeon graphics card is recommended.

Older, and other less efficient graphics cards do not have the required performance and specifications, and offload too much work to the CPU (see below).

The processor is also an important factor, and we recommend using at least and Intel Core 2 Duo, Core i5 or newer architecture processor. AMD processors are also supported, but might exhibit lower performance, as they do not offer the same capabilities and optimizations as Intel CPUs.

### B.1 Minimum requirements

- CPU: Intel Core 2 Duo.
- GPU: OpenGL 2.0 or superior compatible, with pixel-shader support.

### B.2 Recommended configuration

CPU: Intel Core i5 or better.

GPU: AMD/ATI Radeon or nVidia video-card. Intel integrated graphics are not powerful enough and should be avoided.

### B.3 Common requirements

A free USB port to connect the iLok key if not using machine authorization

### **i** Note

Please check the latest version of vendor-provided, optimized drivers are installed for your graphics card. Generic drivers are generally less up-to-date and may contain bugs or miss optimizations present in drivers specific to your particular model.

## **B.4 Compatibility**

FLUX:: Analyzer is a 64bit application fully compatible with 64-bit operating systems.

### **B.4.1 Operating Systems**

- PC: Windows 10
- Apple: macOS versions 10.13 and up (macOS Big Sur, Monterey compliant, Compatible with ARM / Silicon)

### **B.4.2 Hardware IO support**

Any soundcard with a driver compliant with these standards:

- ASIO(Windows).
- Core Audio (macOS).

### **B.4.3 Software - Sample Push support**

SampleGrabber is a 32-bit plug-in compatible using 64-bit double precision internal processing, compatible with 32-bit and 64-bit (via bridge) hosts

All major native formats (AAX, VST, AU, RTAS, TDM, AAX VENUE) are supported.

### **B.4.4 Supported formats**

- Windows 10
  - VST (2.4)
  - RTAS\*
  - TDM\*
  - AAX
  - AAX VENUE

- macOS - 10.12 and later
  - VST (2.4)
  - AU
  - AAX
  - RTAS\*
  - TDM\*

 Warning

\*The TDM/RTAS version requires ProTools version 7 or above.

# C Release Notes

## C.1 FLUX:: Analyser 20.12

### C.2 Major Additions

- Stability improvements (hardening) with all latest operating systems (OS).
- Catalina, Big Sur and Apple notarization official support.
- New built in error reporting tools for FLUX:: Analyser.
- New V20.12 release (new versioning system), now including 1 year of support and upgrade with perpetual license purchase.
- New Apple and Windows menu and shortcuts.
- Many internal improvements and optimizations - CPU and GPU.

### C.3 Major optimizations

- FLUX:: Analyser and Analyser High Precision (64 bit)
- HiDPI / Retina
- Loudness metering conformance for many broadcast/streaming
  - AES Streaming, Apple, Amazon, Deezer, Netflix, Spotify, TIDAL, YouTube and more.
- Revised loudness meter display (clearer, more info and overload warnings)
- Now with 2 perceptual colormaps to spectrogram for improved readability.
- Musical note peak display (label mode)
- Improved spectrum display interpolation
- Improved pure spectrum mode side-lobe analysis
- External IR loading in snapshots
  - visualizing them as impulse responses and magnitude spectra
- I/O layout preference for various channel based arrangements and order.
- OSC support

## C.4 Other Improvements

- Application is now notarized to comply with macOS Catalina, Big Sur requirements.
- Spectrum Frequency scale start at 0Hz
- Limit generator output level to prevent sound card clipping.
- Smoother generator volume changes
- New main menu on macOS (Edit and View Menu)

## C.5 Bug fixes

### C.5.1 FLUX:: Analyser 20.12

#### Build 49931

##### Fixes;

- Studio Session Analyzer is not working

#### Build 49880

##### Fixes;

##### Core:

- Metering Stats (Offline processing) unstable or returning wrong values.
- Metering Stats (Offline processing) file batch loading issue.
- Ensure saved IO setup is still present on reload.
- Fix transfer function magnitude smoothing.
- Limit data tooltips to actual range and fix refresh lag.
- Fix a number crashes that could occur in various scenarios.
- Suppressed some memory leaks.
- Fixed a crash that could occur when switching from pure spectrum / FFT mode.
- Fixed snapshot reload issues.
- Improved network connection stability.
- Added workarounds for various OpenGL driver bugs that were causing display issues on certain setups.
- All sample rates initialized to 48k by default

##### UI:

- Display issues and improvements on macOS

- Added workarounds for various OpenGL driver bugs that were causing display issues on certain setups.
- TruePeak preset name not reflected in UI
- Meter peak value text is clamped to range

Various:

- Fix data races

## **C.5.2 Sample Grabber Plug-ins 20.12**

### **Build 49880**

**Fixes;**

- SampleGrabber base name truncated after close/reopen host.
- SampleGrabber AAX - Win&Mac - Changing the plug-ins layout has no effect on the analyser.
- SampleGrabber - Win&Mac - AAX/AU/VST - GUI issue with Layout list.

## **C.6 Known Issues**

- Wrong channel order with SampleGrabber and Nuendo
  - Issues in some scenarios with Avid VENUE S6L - Sample Grabber AAX VENUE - Doesn't appear to work (works in AAX Native)
-